


How to import EA file into MT5

Step 1

Expert Advisor (EA) is available from the menu or Navigator.


Choose Expert Advisor (EA) from the menu

Click "Insert" in the menu and hover the pointer over "Experts". Choose the Expert Advisor (EA) you want to run.




Choose Expert Advisor (EA) from the Navigator

In the Navigator, click + next to "Expert Advisors". Double-click the Expert Advisor (EA) you want to run, or right-click and select "Attach to Chart".




Or, choose the Expert Advisor (EA) you want to run and drag it to a chart.




Step 2

Once the window for the Expert Advisor (EA) opens, check the "Allow Algo Trading" box.




Step 3

Click the "Inputs" tab to configure the EA settings, if needed. Once you're done--or if no changes are required--click "OK".



Step 4

Click the "Algo Trading" button in the toolbar.




Step 5

Make sure that the Expert Advisor (EA) icon in the top-right corner of the chart is now blue.




Step 6

To configure the Expert Advisor (EA), click "Tools" in the menu and select "Options". (Shortcut keys: "Ctrl"+"O")



Step 7

In the "Expert Advisors" tab, edit the settings and click "OK".



Number	Item name	Descriptions
1	Allow algorithmic trading	Allow the use of Expert Advisors (EA) when checked.
2	Disable algorithmic trading when the account has been changed	Switching the logged-in account will disable trading by the running Expert Advisor (EA) when checked.
3	Disable algorithmic trading when the profile has been changed	Changing the chart profile will disable trading by the running Expert Advisor (EA) when checked.
4	Disable algorithmic trading when the charts symbol or period has been changed	Changing the symbol or timeframe of a chart will disable trading by the running Expert Advisor (EA) when checked.
5	Disable algorithmic trading via external Python API	Disable trading using Python scripts when checked.
6	Allow DLL imports	Allow the Expert Advisor (EA) to use a dynamic link library (DLL) when checked.
7	Allow WebRequest for listed URL	To allow access to external websites, check this checkbox and enter the URL of the website to which you wish to allow access. Ensure that access is granted only to trusted websites to minimize risks.