

RUTINA DE CONTROL DE LAS EXPLOSIONES M.F1

5.1

00010			
00020	EXP1	EQU	56708
00030	EXP2	EQU	56722
00040	EXP3	EQU	56736
00050	NEXP	DEFB	0
00060	DIEXP	DEFW	0
00070	EXP	DEFB	0
00080			
00090	EXP0	LD	A, (EXP)
00100		CP	1
00110		RET	NZ
00120		LD	A, (EXP1+8)
00130		INC	A
00140		CP	3
00150		CALL	Z, PON1
00160		LD	(EXP1+8), A
00170		LD	(EXP2+8), A
00180		LD	(EXP3+8), A
00190		LD	A, (NEXP)
00200		INC	A
00210		CP	7
00220		JR	Z, FINEXP
00230		LD	(NEXP), A
00240		LD	IX, (DIEXP)
00250		LD	A, (IX)
00260		LD	(EXP1), A
00270		LD	A, (IX+1)
00280		LD	(EXP1+1), A
00290		LD	A, (IX+2)
00300		LD	(EXP2), A
00310		LD	A, (IX+3)
00320		LD	(EXP2+1), A
00330		LD	A, (IX+4)
00340		LD	(EXP3), A
00350		LD	A, (IX+5)
00360		LD	(EXP3+1), A
00370		LD	BC, 6
00380		ADD	IX, BC
00390		LD	(DIEXP), IX
00400		CALL	SONI2
00410		RET	
00420			
00430	FINEXP	LD	A, 2
00440		LD	(EXP), A
00450		CALL	MDOWNN
00460		CALL	MDOWNN
00470		CALL	MDOWNN
00480		RET	
00490			
00500	TDE	DEFB	152, 128, 180, 100, 140, 100
00510		DEFB	160, 150, 115, 135, 130, 145
00520		DEFB	169, 125, 130, 112, 170, 145
00530		DEFB	175, 125, 130, 140, 120, 130
00540		DEFB	160, 120, 120, 170, 140, 167
00550		DEFB	125, 156, 163, 143, 153, 120
00560	0		