

15.1) RUTINA DE CONTROL DEL SPEDY M.F1

00010	SPE1	EQU	56670
00020	DEREB	DEFB	0
00030			
00040	SPEDY	LD	A, (E1)
00050		CP	0
00060		JP	Z, RENDB
00070		LD	IY, SPE1
00080		CALL	MOVSP
00090		CALL	CHOSPE
00100		RET	
00110			
00120	MOVSP	CALL	CAMFAB
00130		LD	A, (DEREB)
00140		CP	0
00150		JP	NZ, DEB
00160	IZB	LD	A, (IY+1)
00170		CP	0
00180		JR	Z, FINISB
00190		SUB	B
00200		LD	(IY+1), A
00210		RET	
00220	DEB	LD	A, (IY+1)
00230		CP	200
00240		JR	Z, FINISB
00250		ADD	A, B
00260		LD	(IY+1), A
00270		RET	
00280	CAMFAB	LD	A, (IY+8)
00290		INC	A
00300		CP	3
00310		CALL	Z, PON1
00320		LD	(IY+8), A
00330		RET	
00340	FINISB	CALL	MDOWN
00350		LD	A, 0
00360		LD	(E1), A
00370		RET	
00380	CHOSPE	LD	IY, SPE1
00390		LD	H, 40
00400		LD	L, 48
00410		CALL	CHOQUE
00420		JP	C, MUERTE
00430		RET	
00440			
00450	REND	LD	A, R
00460		AND	%00011111
00470		CP	0
00480		RET	NZ
00490		LD	A, R
00500		AND	%00100000
00510		CP	0
00520		JR	NZ, IZB1
00530		LD	IX, SPE1
00540		CALL	SIZQUI
00550		LD	A, 1
00560		LD	(DEREB), A
00570		LD	(E1), A
00580		LD	A, 0
00590		LD	(SPE1+1), A
00600		LD	A, 144
00610		LD	(SPE1), A

0620	SSPE1	CALL	MUP
0630		LD	HL,SPE1
00640		LD	(T0+1),HL
0650		RET	
0660	IZS1	LD	IX,SPE1
00680		CALL	SDERE
0680		LD	A,0
0690		LD	(DEREB),A
00700		LD	A,1
00710		LD	(E1),A
0720		LD	A,200
0730		LD	(SPE1+1),A
00740		LD	A,92
0750		LD	(SPE1),A
0760		JP	SSPE1
00770			