

CONTROL DE LA VISCOSA

M.F1

00010	VISCO	LD	A, (BAJAR5)	00,
00020		CP	0	
00030		RET	NZ	
00040		LD	A, (EXP)	
00050		CP	2	
00060		JP	Z, VISC2	
00070		CP	1	
00080		RET	Z	
00090		CALL	MOVOJO	
00100		CALL	FALBOC	
00110		CALL	CHOOJO	
00120		LD	A, (BOCA1+8)	
00130		INC	A	
00140		LD	(BOCA1+8), A	
00150		CP	3	
00160		RET	NZ	
00170		LD	A, 1	
00180		LD	(BOCA1+8), A	
00190		RET		
00200	CHOOJO	LD	IY, OJO1	
00210		LD	H, 68	
00220		LD	L, 50	
00230		CALL	CHOQUE	
00240		CALL	C, PATRAS	
00250		CALL	C, MUERTE	
00260		LD	A, 160	
00270		LD	(BOCA1+1), A	
00280		LD	IY, BOCA1	
00290		LD	H, 48	
00300		LD	L, 50	
00310		CALL	CHOQUE	
00320		CALL	C, PATRAS	
00330		CALL	C, MUERTE	
00340		LD	A, 128	
00350		LD	(BOCA1+1), A	
00360		RET		
00370	PATRAS	CALL	MUERTE	
00380		LD	A, (TABLA1+1)	
00390		SUB	24	
00400		LD	(TABLA1+1), A	
00410		LD	A, (TABLA2+1)	
00420		SUB	24	
00430		LD	(TABLA2+1), A	
00440		SCF		
00450		RET		
00460	PALBOC	LD	IY, BOCA1	
00470		LD	H, 48	
00480		LD	L, 50	
00490		CALL	PALO	
00500		RET	NC	
00510		LD	A, (DAT2)	
00520		CP	1	
00530		RET	NZ	
00540		LD	A, (VAR8)	
00550		LD	B, A	
00560		INC	B	
00570		LD	A, (PALOS5)	
00580		ADD	A, B	
00590		LD	(PALOS5), A	
00600		AND	A	
00610		SBC	A, 65	

00620		REI	L
00630		LD	HL,TDE
00640		LD	(DIEXP),HL
00650		LD	A,1
00660		LD	(EXP),A
00670		LD	A,0
00680		LD	(NEXP),A
00690		LD	DE,EXP1
00700		CALL	MUPP
00710		LD	DE,EXP2
00720		CALL	MUPP
00730		LD	DE,EXP3
00740		CALL	MUPP
00750		RET	
00760	BAJAR5	DEFB	0
00770	PALOS5	DEFB	0
00780	MOVQJO	LD	A,R
00790		AND	7
00800		CP	0
00810		JR	Z,M010JO
00820		LD	A,120
00830		LD	(QJO1+1),A
00840		LD	A,(QJO1+8)
00850		INC	A
00860		LD	(QJO1+8),A
00870		AND	A
00880		SBC	A,3
00890		RET	C
00900		LD	A,1
00910		LD	(QJO1+8),A
00920		RET	
00930	M010JO	LD	A,3
00940		LD	(QJO1+8),A
00950		LD	A,96
00960		LD	(QJO1+1),A
00970		RET	
00980	VISC2	LD	A,1
00990		LD	(BAJAR5),A
01000		CALL	RESET
01010		CALL	SPRIPE
01020		CALL	MUP
01030		LD	HL,BOCA2
01040		LD	(T0+1),HL
01050		RET	
01060	BOCA1	DEFB	152,128,0,0,0,0,0,2,1,7
01070		DEFW	BOCAS1,BOCAS2
01080	BOCA2	DEFB	136,160,0,0,0,0,0,1,1,7
01090		DEFW	BOCAS3
01100	QJO1	DEFB	112,120,0,0,0,0,0,3,1,7
01110		DEFW	QJOS2,QJOS3,QJOS1
01120	BOCAS1	DEFB	5,6,0
01130		DEFW	FBOCA1
01140		DEFB	255,000,255,000,128,063,000,247,000,123,000,159,
01150		DEFB	248,000,252,000,000,124,000,123,000,187,000,138,
01160		DEFB	240,007,032,003,000,227,000,155,000,177,000,165,
01170		DEFB	192,015,000,223,000,158,000,221,000,142,000,178,
01180		DEFB	128,063,000,254,000,127,000,166,000,126,000,181,
01190		DEFB	000,113,000,253,000,254,000,087,000,255,000,118,
01200		DEFB	000,078,000,059,000,254,000,155,000,231,000,117,
01210		DEFB	128,042,000,135,000,252,000,188,000,027,000,179,
01220		DEFB	000,115,000,087,000,249,000,186,000,251,000,207,
01230		DEFB	000,114,000,175,000,251,000,062,000,245,000,239,
01			