

ROUTINA DE CONTROL DEL GLOMBAN, M.F2.

00010			
00020	ENEMI1	EQU	56310
00030	TEF2	EQU	54016
00040			
00050	POSDAT	DEFW	TEF2
00060			
00070	VARMA	DEFB	0
00080	VMALO	DEFB	0
00090			
00100			
00110	GLOBO	CALL	CAMBIO
00120		LD	A, (VARMA)
00130		CP	0
00140		JP	Z, STARUP
00150		CP	255
00160		JP	Z, MALOMU
00170		CALL	MOVACT
00180		CALL	MATA
00190		CALL	MATA2
00200		RET	
00210			
00220	STARUP	LD	A, 1
00230		LD	(DAMA4), A
00240		LD	(VARMA), A
00250		LD	HL, TEF2
00260		LD	(POSDAT), HL
00270		LD	A, 0
00280		LD	(VMALO), A
00290		LD	A, 14
00300		LD	(POKEI+1), A
00310		LD	DE, ENEMI1
00320		CALL	MUPP
00330		CALL	DMALO
00340		LD	A, 192
00350		LD	(ENEMI1), A
00360		RET	
00370			
00380	DAMA3	DEFB	0
00390	DAMA4	DEFB	1
00400			
00410	MALOMU	LD	A, (DAMA3)
00420		INC	A
00430		LD	(DAMA3), A
00440		LD	A, (DAMA4)
00450		INC	A
00460		LD	(DAMA4), A
00470		CP	2
00480		JP	Z, MAL11
00490		LD	DE, ENEMI1
00500		CALL	MUPP
00510		RET	
00520			
00530	MAL11	CALL	MDOWNN
00540		LD	A, 0
00550		LD	(DAMA4), A
00560		CALL	SONI2
00570		CALL	SONI1
00580		CALL	SONI2
00590		RET	
00600			

00610	DAMA1	DEFB	0
00620			
00630	MOVACT	LD	A, (DAMA1)
00640		INC	A
00650		LD	(DAMA1), A
00660		CP	2
00670		RET	NZ
00680		LD	A, 0
00690		LD	(DAMA1), A
00700		LD	A, 2
00710		LD	(ENEMI1+8), A
00720		LD	IX, (POSDAT)
00730		LD	A, (IX)
00740		CP	128
00750		CALL	Z, GLOPIE
00760		CP	0
00770		JP	Z, NUTD
00780		LD	(ENEMI1), A
00790		LD	A, (IX+1)
00800		LD	(ENEMI1+1), A
00810		INC	IX
00820		INC	IX
00830		LD	(POSDAT), IX
00840		RET	
00850			
00860	NUTD	LD	IX, TEF2
00870		LD	(POSDAT), IX
00880		JP	MOVACT
00890			
00900	GLOPIE	PUSH	AF
00910		LD	A, 1
00920		LD	(ENEMI1+8), A
00930		POP	AF
00940		RET	
00950			
00960	MATA	LD	IY, ENEMI1
00970		LD	H, 56
00980		LD	L, 56
00990		CALL	CHOQUE
01000		RET	NC
01010		CALL	MUERTE
01020		JP	MUERTE
01030			
01040	DAMA2	DEFB	0
01050			
01060	MATA2	LD	IY, ENEMI1
01070		LD	H, 56
01080		LD	L, 56
01090		CALL	FALO
01100		RET	NC
01110		LD	A, (DAT2)
01120		CP	1
01130		RET	NZ
01140		LD	A, (DAMA2)
01150		INC	A
01160		LD	(DAMA2), A
01170		CP	6
01180		RET	NZ
01190		LD	A, 0
01200		LD	(DAMA2), A
01210		LD	A, (VAR8)
01220		INC	A
01230		LD	B, A
01240		CP	2
01250		JR	Z, SININ
01260		LD	A, (DAMA1)

01270		INC	A
01280		LD	(DADA),A
01290		CP	2
01300		JR	Z,SINON
01310		LD	A,(VMALO)
01320		ADD	A,B
01330		LD	(VMALO),A
01340		RET	
01350			
01360	SINON	LD	A,0
01370		LD	(DADA),A
01380	SININ	PUSH	BC
01390		CALL	VIVE
01400		CALL	SONI1
01410		CALL	SONI2
01420		CALL	SONI3
01430		POP	BC
01440		LD	A,(VMALO)
01450		ADD	A,B
01460		LD	(VMALO),A
01470		AND	A
01480		SBC	A,47
01490		RET	C
01500		LD	A,255
01510		LD	(VARMA),A
01520		RET	
01530			
01540	DADA	DEFB	0
01550			