MAVI Streaming+

UX Scenario Document

App ID	com.mavistreaming.tv
Version	1.1.0
Platform	webOS TV 2018 and later (SDK 4.0.0), 1920×1080, Web app with JS service
Service country / languages	Brazil · UI in Portuguese
Remote	Standard remote and Magic Remote
Website / support	https://mavistreaming.com.br
Date	12 Nov 2026

1. App overview

MAVI Streaming+ is a **media player** for playlists the user already has (Xtream Codes API or M3U link). The app **does not include or sell any channels, movies, series or playlists**; all content comes from the playlist provided by the user.

- **Login:** there is no user account. The user only enters his own playlist (server/user/password or an M3U link). For QA, use the public demo playlist below.
- **Payment:** no in-app purchase. Each TV gets a **7-day free trial** automatically on first launch. After that, the app license is activated on the website mavistreaming.com.br (3rd-party payment outside the app). During QA the trial is active, so no payment or voucher is needed.
- **Ads:** none.
- **Data:** a random device code (generated by the app, not the TV's UDID), the user's playlists, favorites and resume positions are stored to sync between the user's devices. Privacy policy: https://mavistreaming.com.br/privacidade.html
- **Network:** a JS service (com.mavistreaming.tv.service) is used only as an HTTP proxy for playlist servers that do not send CORS headers.

2. How to test

1. Launch the app. The **Adicionar lista** (Add playlist) screen opens.
2. Press ▶ to select **Link M3U**, press ▼ to go to the link field, press OK and type **https://mavistreaming.com.br/demo.m3u**.
3. Select **Salvar e entrar** and press OK. The Home screen opens.
4. The demo playlist contains 1 live channel, 2 movies and 1 series with 2 episodes (public test streams).

> If the trial ever shows as expired on a test device, the activation screen shows a QR code, the MAC and the Device Key. Please contact us through https://mavistreaming.com.br and we will release the device.

3. Screen flow



4. Remote control keys

Key	Action
Arrows	Move focus
OK	Select / play / pause
Hold OK (0.7 s)	Add or remove favorite (channels, movies, series)
BACK	Return to previous screen; on Home, press twice to exit
CH+ / CH−	Page lists; change channel in full screen
Magic Remote	Pointer focuses items, click = OK, wheel = ▲▼
Color keys	Not required (remotes without color keys are fully supported)

01. Add playlist (first launch)



Shown on first launch when no playlist exists. The user chooses **Xtream** (server, user, password) or **Link M3U**, fills the fields with the TV keyboard and selects **Salvar e entrar** (Save and enter). Alternatively the user scans the QR code and adds the playlist on mavistreaming.com.br from a phone; the TV detects it and enters automatically.

Keys: ▲ ▼ move between fields · ◀ ▶ switch Xtream / M3U · OK edit field or press button · BACK (twice) exit app

02. Add playlist – M3U mode



For QA: select **Link M3U**, enter **https://mavistreaming.com.br/demo.m3u** in the first link field and press **Salvar e entrar**. The EPG field is optional and can be left empty.

Keys: Same as above


03. Home



Main menu with five tiles: **AO VIVO** (Live TV), **FILMES** (Movies), **SÉRIES** (Series), **LISTAS** (Playlists) and **AJUSTES** (Settings). The bottom cards show the active playlist, the app status (free trial / active, expiry date, version) and the device key.

Keys: ◀▶ select tile · OK open · BACK twice exit app (toast "Aperte VOLTAR de novo para sair")


04. Live TV



Left: categories (Favorites, All, provider categories). Middle: channels of the selected category. Right: preview of the selected channel and program guide (EPG) when the playlist provides it.

Keys: ▲ ▼ move · ◀ ▶ change column · OK on a channel: play in preview, OK again: full screen · hold OK: add/remove favorite · CH+/CH- page

05. Live TV – full screen



Full-screen playback with channel badge and now/next information.

Keys: ▲ ▼ / CH+/CH- previous/next channel · OK show info · BACK return to list

06. Movies



Categories on the left and a poster grid on the right. The **Series** section uses the same layout.

Keys: Arrows move · OK open details · hold OK: favorite · BACK return


07. Movie details



Cover, rating, year, duration, genre and synopsis (from the user's playlist). Buttons: **Assistir** (Play) or **Continuar** (Resume) and **Favoritar** (Favorite).

Keys: ◀▶ select button · OK confirm · BACK return


08. Player (movies / episodes)



Video player with title, progress bar and time. When the stream has more than one audio track or subtitles, **Áudio** and **Legenda** buttons appear in the bottom bar. Playback position is saved automatically (resume).

Keys: OK play/pause · ◀▶ seek 10 s · ▼ audio/subtitle buttons · BACK stop and return


09. Series details



Seasons and episode list; the main button resumes the last watched episode.

Keys: ▲ ▼ move · ◀ ▶ seasons/buttons · OK play episode · BACK return


10. Next episode countdown



60 seconds before the end of an episode a small box shows **Próximo episódio em 60s** (Next episode in 60 s), the series name and episode, and plays the next episode automatically when the counter ends.

Keys: OK play now · BACK cancel countdown

11. Playlists



List of the user's playlists. Select a playlist to use it, **+ Adicionar lista** to add another one, or the trash icon to delete it (asks for confirmation).

Keys: ▲ ▼ move · ▶ trash icon · OK confirm (OK twice to delete) · BACK return

12. Settings



Device key, status of the free trial/subscription, app version, website, and **Recarregar listas** (Reload playlists).

Keys: OK reload · BACK return