


AWS S3 Transfer Acceleration: -

Summary: -


In this lab, I configured AWS S3 Transfer Acceleration to improve file upload speed to an S3 bucket located in another region. I created an S3 bucket outside India, configured AWS CLI using access keys, and uploaded files through Command Prompt. First, I tested the normal upload speed with Transfer Acceleration disabled, then enabled Transfer Acceleration from the bucket properties and used the acceleration endpoint to upload files again. After enabling it, the file transfer speed improved and the file was uploaded successfully to the S3 bucket

Let's Start: -

- Amazon S3 Transfer Acceleration (S3TA) can make uploading and downloading files to and from Amazon S3 much faster, especially for users far away from the S3 bucket
- S3TA helps you transfer files faster and more consistently by using advanced routing and a global network, and it's simple to set up.
- Test [Link](#).
- Now we need to create a s3 bucket in other region outside from India.



- My bucket is created now we need to upload data.
- But we can't upload with UI we need to upload data with Command Prompt.
- So open Command Prompt.




- Enter aws configure.


```
Microsoft Windows [Version 10.0.19045.7291]
(c) Microsoft Corporation. All rights reserved.

C:\Users\Akash Kumar>aws configure
AWS Access Key ID [*****DKT6]:
```

- Now we need access key id.
- So go to your aws console in your browser.



- Now click your name and then select Security Credentials.



- Now scroll down and click Create access key.

Access key best practices & alternatives [Info](#)

Avoid using long-term credentials like access keys to improve your security. Consider the following use cases and alternatives.

Use case



Command Line Interface (CLI)

You plan to use this access key to enable the AWS CLI to access your AWS account.



Local code

You plan to use this access key to enable application code in a local development environment to access your AWS account.



Application running on an AWS compute service

You plan to use this access key to enable application code running on an AWS compute service like Amazon EC2, Amazon ECS, or AWS Lambda to access your AWS account.



Third-party service

You plan to use this access key to enable access for a third-party application or service that monitors or manages your AWS resources.

- Select CLI and scroll down click next.

Set description tag - *optional* [Info](#)

The description for this access key will be attached to this user as a tag and shown alongside the access key.

Description tag value

Describe the purpose of this access key and where it will be used. A good description will help you rotate this access key confidently later.

Maximum 256 characters. Allowed characters are letters, numbers, spaces representable in UTF-8, and: _ . : / = + - @

[Cancel](#)

[Previous](#)

[Create access key](#)

- Now simply click create access key.

Retrieve access keys [Info](#)

Access key

If you lose or forget your secret access key, you cannot retrieve it. Instead, create a new access key and make the old key inactive.

Access key



AKIAWX44AK7X5ITQVV2U

Secret access key



***** [Show](#)

- Now we have both access key and secret access key.
- Copy access key now.

```
Command Prompt - aws configure
Microsoft Windows [Version 10.0.19045.7291]
(c) Microsoft Corporation. All rights reserved.

C:\Users\Akash Kumar>aws configure
AWS Access Key ID [*****DKT6]: AKIAWX44AK7X5ITQW2U
AWS Secret Access Key [*****BfrU]: █
```

- Then paste access key and secret access key.

```
Command Prompt
Microsoft Windows [Version 10.0.19045.7291]
(c) Microsoft Corporation. All rights reserved.

C:\Users\Akash Kumar>aws configure
AWS Access Key ID [*****DKT6]: AKIAWX44AK7X5ITQW2U
AWS Secret Access Key [*****BfrU]: futIe7plFB2ALBuWkFPT+cp18xUolviT5XtR6vY
Default region name [us-west-2]: ap-south-1
Default output format [None]: json

C:\Users\Akash Kumar>█
```

- Now Enter region name according to you.

```

Command Prompt
C:\Users\Akash Kumar\Downloads>cd myusa

C:\Users\Akash Kumar\Downloads\myusa>ls
'ls' is not recognized as an internal or external command,
operable program or batch file.

C:\Users\Akash Kumar\Downloads\myusa>dir
Volume in drive C has no label.
Volume Serial Number is CC63-EC96

Directory of C:\Users\Akash Kumar\Downloads\myusa

22-05-2026  16:47    <DIR>          .
22-05-2026  16:47    <DIR>          ..
27-04-2026  11:36                26,216,840 python.exe
               1 File(s)                26,216,840 bytes
               2 Dir(s)  51,154,010,112 bytes free

C:\Users\Akash Kumar\Downloads\myusa>

```

- Go to folder where your file is present.
- Now see I go to download in folder myusa and check file is present or not.
- Now go to your bucket tab in your browser.

my-us-bucket23 Info

Objects | Metadata | **Properties** | Permissions | Metrics | Management | File systems - new | Access Points

Bucket overview

AWS Region

US East (N. Virginia) us-east-1

Amazon Resource Name (ARN)

arn:aws:s3::my-us-bucket23

Creation date

May 22, 2026, 16:26:48 (UTC+05:30)

- Go inside Properties.
- Scroll down.

Transfer acceleration

Edit

Use an accelerated endpoint for faster data transfers. [Learn more](#)

Transfer acceleration

Disabled

- Now See our Transfer acceleration is currently disabled.
- Firstly we check speed with disabled.
- Go to cmd

```
C:\Users\Akash Kumar\Downloads\myusa>aws s3 cp python.exe s3://my-us-bucket23
Completed 6.0 MiB/25.0 MiB (882.6 KiB/s) with 1 file(s) remaining
```

- Enter `aws s3 cp {filename.extension} s3://{BucketName}`
- Now See this is the speed before enable transfer acceleration.
- Now check after enable.
- Firstly go to bucket tab.

Edit transfer acceleration [Info](#)

Transfer acceleration

Use an accelerated endpoint for faster data transfers. [Learn more](#)

Transfer acceleration

- ☐ Disable
☒ Enable

Accelerated endpoint

☐ my-us-bucket23.s3-accelerate.amazonaws.com

 Use the accelerated endpoint for faster data transfers, which will incur an additional fee. See [Amazon S3 pricing](#)

[Cancel](#)

[Save changes](#)

- Enable it and copy Acceleration endpoint.
- Firstly delete the uploaded file and go back to CMD.

```
C:\Users\Akash Kumar\Downloads\myusa>aws s3 cp python.exe s3://my-us-bucket23 --region ap-
south-1 --endpoint-url https://my-us-bucket23.s3-accelerate.amazonaws.com
Completed 8.0 MiB/25.0 MiB (2.1 MiB/s) with 1 file(s) remaining
```

- Now Enter `aws s3 cp {filename.extension} s3://{BucketName} --region ap-south-1 --endpoint-url https://{Paste Acceleration endpoint}`
- Now see file is uploaded or not.

my-us-bucket23/

Copy S3 URI

Objects

Properties

Objects (1)

Copy S3 URI

Copy URL

Download

Open

Delete

Actions

Create folder

Upload

Objects are the fundamental entities stored in Amazon S3. You can use [Amazon S3 inventory](#) to get a list of all objects in your bucket. For others to access your objects, you'll need to explicitly grant them permissions. [Learn more](#)

Find objects by prefix

< 1 >

	Name	Type	Last modified	Size	Storage class
	python.exe	exe	May 22, 2026, 17:11:36 (UTC+05:30)	25.0 MB	Standard

- File is uploaded.