

Week 2

```
pranav_chowdary@Pranav: ~  
pranav_chowdary@Pranav:~$ nano q2.c  
pranav_chowdary@Pranav:~$ gcc q2.c  
pranav_chowdary@Pranav:~$ ./a.out  
File copied successfully  
pranav_chowdary@Pranav:~$ echo "Hello, this is a Linux system call program." > source.txt  
pranav_chowdary@Pranav:~$ gcc q2.c -o q2  
./q2  
File copied successfully  
pranav_chowdary@Pranav:~$ cat copy.txt  
Hello, this is a Linux system call program.  
pranav_chowdary@Pranav:~$ sudo apt install strace  
[sudo: authenticate] Password:  
Installing:  
  strace  
  
Installing dependencies:  
  libunwind8  
  
Summary:  
  Upgrading: 0, Installing: 2, Removing: 0, Not Upgrading: 101  
  Download size: 737 kB  
  Space needed: 2660 kB / 1024 GB available  
  
Continue? [Y/n] y  
Get:1 http://archive.ubuntu.com/ubuntu resolute/main amd64 libunwind8 amd64 1.8.3-0ubuntu1 [59.6 kB]  
Get:2 http://archive.ubuntu.com/ubuntu resolute/main amd64 strace amd64 6.19+ds-0ubuntu5 [678 kB]  
Fetched 737 kB in 1s (1066 kB/s)  
Selecting previously unselected package libunwind8:amd64.  
(Reading database ... 48259 files and directories currently installed.)  
Preparing to unpack .../libunwind8_1.8.3-0ubuntu1_amd64.deb ...  
Unpacking libunwind8:amd64 (1.8.3-0ubuntu1) ...  
Selecting previously unselected package strace.  
Preparing to unpack .../strace_6.19+ds-0ubuntu5_amd64.deb ...  
Unpacking strace (6.19+ds-0ubuntu5) ...
```

```
pranav_chowdary@Pranav:~$ strace cat source.txt
execve("/usr/bin/cat", ["cat", "source.txt"], 0x7ffea630f9b8 /* 25 vars */) = 0
brk(NULL)                               = 0x5f89636bd000
mmap(NULL, 8192, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_ANONYMOUS, -1, 0) = 0x7af68f4db000
access("/etc/ld.so.preload", R_OK)      = -1 ENOENT (No such file or directory)
openat(AT_FDCWD, "/etc/ld.so.cache", O_RDONLY|O_CLOEXEC) = 3
fstat(3, {st_mode=S_IFREG|0644, st_size=28563, ...}) = 0
mmap(NULL, 28563, PROT_READ, MAP_PRIVATE, 3, 0) = 0x7af68f4d4000
close(3)                                = 0
openat(AT_FDCWD, "/usr/lib/x86_64-linux-gnu/libselinux.so.1", O_RDONLY|O_CLOEXEC) = 3
read(3, "\177ELF\2\1\1\0\0\0\0\0\0\0\3\0-\>\0\1\0\0\0\0\0\0\0\0\0\0...", 832) = 832
fstat(3, {st_mode=S_IFREG|0644, st_size=199120, ...}) = 0
mmap(NULL, 206288, PROT_READ, MAP_PRIVATE|MAP_DENYWRITE, 3, 0) = 0x7af68f4a1000
mmap(0x7af68f4a8000, 135168, PROT_READ|PROT_EXEC, MAP_PRIVATE|MAP_FIXED|MAP_DENYWRITE, 3, 0x7000) = 0x7af68f4a8000
mmap(0x7af68f4c9000, 28672, PROT_READ, MAP_PRIVATE|MAP_FIXED|MAP_DENYWRITE, 3, 0x28000) = 0x7af68f4c9000
mmap(0x7af68f4d0000, 8192, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_FIXED|MAP_DENYWRITE, 3, 0x2f000) = 0x7af68f4d0000
mmap(0x7af68f4d2000, 5584, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_FIXED|MAP_ANONYMOUS, -1, 0) = 0x7af68f4d2000
close(3)                                = 0
openat(AT_FDCWD, "/usr/lib/x86_64-linux-gnu/libgcc_s.so.1", O_RDONLY|O_CLOEXEC) = 3
read(3, "\177ELF\2\1\1\0\0\0\0\0\0\0\3\0-\>\0\1\0\0\0\0\0\0\0\0\0\0...", 832) = 832
fstat(3, {st_mode=S_IFREG|0644, st_size=187120, ...}) = 0
mmap(NULL, 182526, PROT_READ, MAP_PRIVATE|MAP_DENYWRITE, 3, 0) = 0x7af68f473000
mmap(0x7af68f477000, 147456, PROT_READ|PROT_EXEC, MAP_PRIVATE|MAP_FIXED|MAP_DENYWRITE, 3, 0x4000) = 0x7af68f477000
mmap(0x7af68f49b000, 16384, PROT_READ, MAP_PRIVATE|MAP_FIXED|MAP_DENYWRITE, 3, 0x28000) = 0x7af68f49b000
mmap(0x7af68f49f000, 8192, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_FIXED|MAP_DENYWRITE, 3, 0x2c000) = 0x7af68f49f000
close(3)                                = 0
openat(AT_FDCWD, "/usr/lib/x86_64-linux-gnu/libm.so.6", O_RDONLY|O_CLOEXEC) = 3
read(3, "\177ELF\2\1\1\3\0\0\0\0\0\0\3\0-\>\0\1\0\0\0\0\0\0\0\0\0\0...", 832) = 832
fstat(3, {st_mode=S_IFREG|0644, st_size=1198376, ...}) = 0
mmap(NULL, 1208152, PROT_READ, MAP_PRIVATE|MAP_DENYWRITE, 3, 0) = 0x7af68f34d000
mmap(0x7af68f35f000, 655360, PROT_READ|PROT_EXEC, MAP_PRIVATE|MAP_FIXED|MAP_DENYWRITE, 3, 0x12000) = 0x7af68f35f000
mmap(0x7af68f3ff000, 466944, PROT_READ, MAP_PRIVATE|MAP_FIXED|MAP_DENYWRITE, 3, 0xb2000) = 0x7af68f3ff000
mmap(0x7af68f471000, 8192, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_FIXED|MAP_DENYWRITE, 3, 0x123000) = 0x7af68f471000
close(3)                                = 0
openat(AT_FDCWD, "/usr/lib/x86_64-linux-gnu/libc.so.6", O_RDONLY|O_CLOEXEC) = 3
```


