

DCS SORTIE STARTER

USER GUIDE

Pick a map, an era, and an aircraft — fly a living world in minutes.

Airfields dressed. SAMs up. The strike group at sea. Your flight plan stays yours.

VERSION 1.112.0

Developed by Authentic Media LLC · robgrady.com · provided as-is - no warranty, no liability · 1

Select, don't search. Get a living DCS mission with period-inspired settings in under a minute — no editor, no Lua. We set the stage, you write the play: you are never handed a flight plan you did not ask for — and there is no waypoint editor, because none is needed. Waypoints appear only where the mission itself calls for them: a routed strike (the strike templates), a curated training ride whose printed syllabus IS the flight plan (the White Knights rides carry the squadron's own route, because the route is the lesson), or the **Automatic waypoints** tickbox you switch on yourself.

The four doors

✘ **Fly Now** — the fastest path. One screen, three picks: what do you want to practice (Tanker Time, BFM Merge, Kill the Guns, Beat the SAM), in what, and where. Era, base, weather and comms are derived for you; a single "spice" notch sets the opposition (calm / realistic / hostile) and the ✘ re-rolls a fresh layout of the same picks. Tanker Time and BFM Merge start you **airborne** — behind the tanker at its assigned block, or in your chosen BFM geometry.

✘ **Library** — find individual **Missions** or multi-mission **Collections**. Search titles, aircraft/nicknames, maps, activities and collection mission names. Expand **Filters & sort** for aircraft, map, era, activity, mission setup and **Threat** (opposition intensity, not pilot skill). Three featured picks appear when unfiltered; each appears only once. Collection cards show their mission count and fixed requirements.

Use **My DCS content** to declare installed maps, aircraft and additional modules such as Supercarrier. These preferences stay on this device. **Compatible with my content** checks all requirements of a fixed collection; unknown or incomplete requirements remain unconfirmed and are excluded. For configurable missions, it looks for a matching aircraft, era and map and opens that combination in the detail view. Changing those selections refreshes the summary. Generate from the detail or **Customize in Builder**. Ownership is your declaration, not an inspection of your DCS installation.

A collection download contains its authored missions and does not change with Builder selections. The detail lists the flying sequence and separate Mission and Briefing links. Historical dates, classifications and sources remain in the setting disclosure. **Train** organizes the same rides into a learning sequence and records progress in this browser.

✘ **Train** — the Training Pipeline. Learn it, fly it, fight it. Three schools in the order every air force runs them: Ground School and UPT (the history chapter, then fly an airplane — formation, timing, the tanker, in any jet), FRS — Know Your Jet (the contact phase, systems, the squadron's tactical checkout, weapons, and a check ride), MQT — Fight the Jet (employment). Every ride is a generated Library mission with its brief and kneeboard; where the Mission Editor can see what you are doing it grades you and opens a scorecard, and where it cannot the card says so. Units that are not built yet are shown as **planned**, with the reason. Tick units done as you fly them to the standard on their brief — the record lives in your browser and nowhere else. A virtual squadron takes the **squadron kit** (printed program, a gradesheet with one row per ride, the readings) and downloads the missions from each track. The first course is the F-4E Phantom II.

✘ **Builder** — the full wizard. Theater, era, coalition, aircraft, airfield dressing, the Threat Dial (including the guns-only tier: AAA belts, zero SAMs), support, corridors, map graphics — everything, in seven screens.

Mission readiness before Generate

Builder's Review, configurable Library mission details and Fly Now show a **Mission readiness** card. It checks the effective recipe and lists terrain, player aircraft and known ship-module requirements. **Your content** compares these requirements with your declaration in Library → My DCS content; it cannot inspect your

installation. It identifies human aircraft and veteran AI wingmen, or says an authored flight will be counted after generation. Aircraft counts exclude cockpit crew positions; use the mission briefing and module's join instructions for a human crewmate.

Ground departures show size-compatible stands before allocation and the number with measured static-aircraft directions. Remaining stands use field or geometric defaults. These measurements govern statics, not player taxi behavior; generation still allocates parking and may select a different friendly field when required. Carrier deck allocation happens during generation. Stores are composed then; inspect **Your loadout** in the resulting Mission Kit.

Selection checked does not mean the sortie was flown. The card names the app release and explicitly marks DCS flight validation **unverified**. AI/support assets, installed module versions and every mod dependency are not fully certified. Read generation warnings and DCS load warnings. A failed setup check explains which selection needs correction. If the check is unavailable, Generate still performs the engine's compatibility checks.

Your mission kit

Every generate ends with the **Mission Kit**: the .miz (with its install path), the **briefing pack** (a PDF — SITUATION/MISSION/EXECUTION brief, theater chart with the numbered threat order of battle, comms/nav card with diverts and fuel boxes — plus Markdown for Discord), the **kneeboard** riding in-jet (RShift+K: comms card, airfield data, theater overview with the live threat rings), the loaded **flight plan** on routed strike missions, and the **DTC setup card** for the F-14B(U). On the **Nevada map the flight plan is threaded through the Nellis corridors** — the FLEX turnout, the Sally Corridor or the Alamo Corridor to the north ranges, FYTTR and Indian Springs to the south range, the west road round the Box, and a published recovery home — with the corridors and gates drawn on the F10 map and briefed with their sources. On the **Syria map** the same standard applies — the Levant corridors: from the Galilee fields up the coast and over the Bekaa, or J14 to Rosh Pina and over Hermon; from Akrotiri the SIDs to IREFA and the sea road to NIKAS; from Incirlik the W74 Northern Watch road and the Hatay and Kilis gates; from Muwaffaq Salti the Amman TMA and L200 to Al-Tanf — with a Levant chart in the kneeboard and the brief. On **Cold War Germany** (Cold War era only) it is the Central Region of 1985, either side of the line: from the Eifel, the Hunsrück, the Pfalz and Rhein-Main over the Taunus to the Low Level Transit Routes through the HAWK belt — the Fulda Gap at Point Alpha, the Werra at Herleshausen, the Harz road to Helmstedt, the Hof corridor; from the Rhineland and the Weser the A2 to Helmstedt and the Heath to the Elbe crossings; and, flying red, from the Berlin ring, Merseburg or Parchim along the GDR's own flight lines to the same six gates. The ADIZ, the HAWK and Nike belts, the Berlin corridors, the LFAs and the ranges are on the chart.

Formation: the position ladder

The formation stages put a small card on the LEFT of your screen at eye level — the same side lead is on, clear of the comms menu and the message log — that names the one input to make: **HOLD, ADD POWER, EASE OFF, COME UP, COME DOWN, OPEN OUT, REJOIN**, and **STEADY**, which means "you are out of position but already closing at the right rate, so add nothing". Read it with the edge of your vision; you should never have to leave lead to use it. A ladder at the top shows your range — CLOSE, SLOT, OUT, LOST. It cannot show left/right (the mission measures range from lead, not which side you are on), so lateral comes from the sight picture. Turn it off any time with F10 → FORMATION: turn the position ladder OFF.

Can't see it? F10 → FORMATION: show the position ladder now draws one immediately. Do that on the ramp before you take off: if a card appears, the ladder is working and will follow you all sortie; if nothing appears, the

picture is not rendering on your machine and the sortie is not the place to find that out. While the ladder is fitted, lead stops nagging you in the corner — the card says it, so the text does not repeat it.

Lead also waits for you: at the first two route points he orbits until you have been in the slot for fifteen seconds, then flies the profile. He gives up after a few minutes and goes anyway. Neither happens on a check ride.

Quick start (Builder path)

1. Pick a **map** and an **era**. The era is a hard filter: a WWII starter will not offer you a Hornet, and a modern starter will not offer a Spitfire.
2. Pick **who's flying** (just you, or a 2-4 ship), your side, home airfield, and aircraft. Choose **Veteran AI wingmen** to replace some human seats with AI pilots in your flight.
3. Toggle **building blocks** (everything is optional — defaults are sensible).
4. **Generate** — your Mission Kit appears and the .miz downloads. Drop it in Saved Games/DCS/Missions/ and fly, or open it in the Mission Editor.
5. **Share** — "Copy share link" regenerates this exact mission for anyone: the same recipe + seed reproduces the mission within the same generator release.

Privacy note: we count what missions get generated (map, aircraft, mission type) to decide what to build next — never who generated them.

Flying with veteran AI wingmen

In **Builder** → **Flight** → **Who's flying**, choose **4-ship** and set **Veteran AI wingmen** to **3** for your aircraft plus three AI wingmen. This creates a single-player mission: put the .miz in Saved Games/DCS/Missions/ and fly. The wingmen use DCS **High** skill, the level labelled veteran here, and belong to your own flight. Use the wingman radio menu to command them.

For a two- or three-ship, you can likewise assign up to one or two AI wingmen. If two or more aircraft remain human seats, they are multiplayer clients; host the mission through **Multiplayer** → **New Server**. Leave the AI count at **None** — **human seats** to keep the existing multiplayer setup. Reducing flight size reduces the AI count as needed to retain at least one human aircraft. Share links and saved Builder settings retain this choice.

All aircraft in the flight use the selected airframe and loadout. AI wingmen follow native DCS behavior; this option does not script attack geometry or formation procedures. Fixed crew-ops flights and authored Case III recovery rides do not offer this option. Existing training rides retain their authored wingmen when no custom AI count is selected.

The standard comm ladder

Every starter uses the same predefined comms, so learn it once:

Ch	Agency	Callsign	Freq (UHF)	TACAN	Notes
1	Your flight	(varies)	305.725	—	flight common — DCS loads it on CH 1
2	Carrier	Mother	264.425	71X	ICLS 11 · Link4 336 · ACLS on

3	AWACS	Overlord	251.475	—	land-based E-3/A-50
4	Tanker	Texaco	253.625	39Y	speeds/altitudes per type
5	Plane guard	Angel	262.050	—	carrier flight ops
6	CAP	(squadron)	258.175	—	carrier air wing
7	Tactical	—	254.325	—	inter-flight coordination
8	AEW Hawkeye	(squadron)	259.925	—	carrier air wing (CH 3 when there is no AWACS)
last	Guard	—	243.000	—	monitored — fixed by regulation
—	FARPs	(name)	127.525+	—	0.25 steps per pad

The same ladder is printed on the in-jet **kneeboard** (comms card page) and in the mission briefing, and it is loaded into every UHF preset radio the jet has (both sets in an F-14 or a Hornet). All carrier systems are pre-activated: TACAN 71X "STN", ICLS channel 11, Link4 on 336, and ACLS — tune and go.

Your own comm plan

Squadrons have their own SOP. In the Builder, **Support & presentation** → **Comm plan** shows the ladder as a table: a Default column and a This mission column. Leave it alone and nothing changes. Overwrite a cell and everything that prints or programs that frequency follows — the tanker's own radio, the AWACS, the boat, the cockpit presets, the card, the kneeboard and the F-14B(U) DTC page — and the card marks the row custom.

What the table refuses, and why: **Guard** is 243.000 by regulation and cannot be moved; a frequency **off the 25 kHz raster** (253.630) is refused with the nearest channel named, because no radio can tune it; a frequency **outside UHF 225–400** is refused unless the aircraft's own radios reach it (a Mustang's VHF flight frequency is fine for a Mustang). Two rows on one frequency are allowed with a warning — co-channel is legal, sometimes intended, often a slip. **Channels are fixed**: that is what makes the plan learnable across every starter.

Profiles save a set of overrides in this browser under a name ("Squadron SOP") and fill the table on demand. The overrides ride in the recipe, so a **share link** reproduces the mission with the custom plan — the wingman does not need the profile. Copy JSON gives the overrides as a comms block for the API (`{ "comms": { "tanker": 271.5 } }`).

Building blocks

- **Airfield dressing** — era/faction-correct static aircraft on real parking stands, ground support equipment, fuel farms, tents, comms towers. Density: sparse/normal/busy.

- **Air defenses** — complete, functional SAM sites with doctrinal layouts (SA-2/3/6/11, Hawk, Patriot by era/side) plus SHORAD at fields. WWII gets flak, not SAMs, and the **War on Terror** era gets no SAMs at all — the threat there is truck-mounted and emplaced guns, dense and low, and the Threat Dial scales the gun line.

- **Enemy air** — CAP flights and the BFM adversary spawn with an era- and role-correct weapons fit: a 1978 MiG-21 carries R-13Ms and R-60s, a modern MiG-29S carries R-27ERs, R-77s and R-73s. You never pick the enemy's loadout — era and mission type imply it — but you are always told what it is. Look for the **ENEMY AIR** block on the theater chart and on the in-jet kneeboard: it names the fit and what it means for how you fight him. At Threat Dial intensity 1–2 the bandits carry a lighter fit, so the dial changes the character of the fight and not only the head count.

- **Tanker / AWACS** — on station behind friendly lines with the standard freqs above. Not available in WWII (no AAR or AWACS in 1944 — the era gate is strict). In the **War on Terror** era there is no red AWACS, because there is no red air force.

- **Carrier strike group** — see below.

- **Ambient air traffic** — AI transports starting up and flying between friendly fields.

- **Pattern traffic** — AI aircraft recovering into, or departing from, your own field at mission start (landing / takeoff / both; fighters, cargo, helicopters or mixed; up to 8 aircraft). Formation departures — departing aircraft lining up on the runway and rolling as two-ship sections, using DCS 2.9.30's AI runway line-up — appears here once the feature's encoding has been verified against a Mission-Editor-saved file; until then the option is not offered rather than offered and ignored.

- **Functional FARPs** — pads with the fuel/ammo/command/comms vehicles required for rearm/refuel to actually work.

- **Strike targets** — depot / convoy / C2 packages in the enemy rear, each with a trigger zone ready for your own mission logic.

- **Practice range** — bombing ring and strafe line in the friendly rear.

- **Nav kneeboard** — comms card, airfield data (runways, stands), and a theater overview schematic, rendered into the jet's kneeboard.

The carrier strike group

Pick a hull and you get its **real strike group**: the Roosevelt sails as CSG-9 with USS Lake Erie (CG-70) and DESRON 23 destroyers; the Truman as CSG-8 with USS Gettysburg; the Forrestal as a 1980s Med battle group with USS Ticonderoga. Screen stations follow doctrine: plane-guard destroyer astern, AAW cruiser on the beam, pickets on the bow quarters. The group steams into wind on BRC.

Deck configuration follows real spotting practice:

- **Recovery** — the landing area is clear (angle, waist cats, EL4, port stern); the bow is packed in tight uniform herringbone rows across the cat tracks, E-2s nose-out on the point, helos in the corral.

- **Launch** — cats, JBDs, and taxi flow clear; spares spotted aft.

- **Packed** — port-visit deck, everything fouled including the angle. No-fly.

Check the aircraft types you want on deck; rows are spotted one squadron per row. Deck equipment (tugs, MJ-1 loaders, crash gear) sits at real stations. Optionally launch the air wing's **CAP** (2-ship on the threat axis at 25k, e.g. VFA-146 Blue Diamonds) and **E-2 Hawkeye** AEW orbit covering the force.

Template packs

- **Crew Ops: Jester IZLID Strike (F-14B(U), pilot seat)** — you fly;

Jester operates the back seat. Run designation from the F10 CREW menu: start the IZLID, confirm its effect, then cease. Progress is player-paced.

- **Crew Ops: Iceman GCI Intercept (F-14B(U), RIO seat)** — command the AI pilot from the F10 CREW menu while running the intercept from the pit.

- **RIO Fleet Defense (F-14A/B)** — use the cockpit Iceman menu in solo play, or fly with a human crewmate. It does not use the B(U) mission-command API.

The F-4E training rides are a separate course; these F-14 crew-command features do not apply to the Phantom.

Templates are one of the three places waypoints appear (the AI pilot needs steerpoints to fly). The second is a **curated training ride** — the White Knights rides carry the squadron's own route automatically, since flying that exact ground track is the lesson. The third is **Automatic waypoints**, the tickbox on the Targets screen — off unless you turn it on, and it builds WP1 → IP → TARGET → home with a kneeboard leg card to fly it off.

Share links & recipes

A starter is defined by its **recipe** (your wizard selections + a seed). Share links encode the recipe, not the file. Within one generator release, the same recipe and seed reproduce the same mission. Later releases may correct content or update DCS compatibility while retaining the recipe; keep the downloaded `.miz` when you need an exact archived mission. Change the seed to reroll the details while keeping your selections.

Missions through an AI assistant (MCP)

An MCP-compatible assistant can connect to <https://dcs-mission-starter.fly.dev/mcp/> using **Streamable HTTP**. Add this URL as a remote MCP server in your assistant's settings; configuration names vary by client. Sortie Starter's public tools do not require a login. The public agent guide is available at [/api/mcp-guide](#), indexed by [/llms.txt](#), and as the MCP resource [sortiestarter://integration-guide](#).

Ask the assistant to search the catalog, inspect a mission's requirements, validate your selections, and generate a mission. For example: “Build a modern Caucasus F-16 four-ship with three veteran AI wingmen and a kneeboard.” You still need to own the relevant DCS map and aircraft modules.

Generation returns a mission manifest plus links to the **mission .miz** and **full mission kit ZIP**. Download and unzip the kit, then put `mission.miz` in `Saved Games/DCS/Missions/`. Use single-player for one human aircraft and multiplayer for two or more human seats. Available briefs, kneeboard PNGs, DTC setup card, `comms.json`, and `navigation.json` accompany the mission. DTC files are supplied only when the selected aircraft supports them and rendering succeeds. Check the manifest's file list and warnings.

Links regenerate the recipe on the stated app version and check its native mission checksum. If mission content changes, ask for fresh links. After a deployment, a link from an older version returns “another app

version”; ask the assistant to generate fresh links. Keep downloaded files for an exact archive. A busy generator asks you to retry after three seconds. Recipe validation checks fields and template defaults; generation makes the final compatibility checks.

The assistant's recipe schema includes numeric limits and the human-seat rule: **1–4 aircraft**, with **0–3 veteran AI wingmen** and always at least one human aircraft. Other bounds include parking fill (0–100%), pattern traffic (1–8), threat intensity (1–5) and timing hold (0–15 minutes). Fixed crew-ops and Case III rides still refuse custom veteran wingmen. Validate the selected recipe before generation; these limits do not replace the final compatibility checks.

Published packs remain authored downloads: the assistant retrieves their pack link rather than rebuilding a pack_ template. Missions are not saved in an account or installed in another application. A specific F-14B(U)/Caucasus native import was tested in DKS; see below for what survived. This connection does not place files in its ATO.

Importing a mission into Digital Kneeboard Simulator

Download and unzip the Mission Kit. In DKS choose **New kneeboard** → **Import .miz**, select mission.miz and the human flight, then review and create the design. Import the native mission, not the kit ZIP. DKS designs belong to a squadron; an unpublished test design is still visible to its squadron members.

The v1.112.0 F-14B(U)/Caucasus test retained the player aircraft, takeoff and route coordinates, route altitude/speed/elapsed times, radio frequencies, tanker/AWACS details, stores and mission map drawings. Its one human aircraft appeared in the crew roster; three AI wingmen did not become human roster rows. Radio **agency names** remained blank. DKS displayed landing as an unnamed steerpoint with no ETA, and its additional-point/plot-line lists were empty. Its cartridge sections used aircraft defaults. Native cartridge import/export, in-cockpit loading, other aircraft/maps, kneeboard export size and ATO posting remain unverified.

Keep comms.json, navigation.json, brief and DTC setup card beside the mission for comparison. These JSON sidecars are integration references, not a DKS import format. DKS can recalculate a flight plan; compare its results with the original mission before exporting a replacement cartridge. Preserve the original .miz when exact mission bytes matter.

FAQ

The mission won't load / units are missing. Make sure you own the map, and for carrier decks with CVN-71/72/73/75 you need the Supercarrier module (the Stennis deck works in the base game; the Forrestal comes with the F-14).

Can I edit the starter? Yes — that's the point. Open it in the Mission Editor; everything is ordinary groups and statics you can move, delete, or build on.

Why can't I pick aircraft X in era Y? Hard era gate by service window — e.g. the Hornet entered service in 1987, so it can't appear in a Cold War (1965–1985) starter. This is a broad era filter, not certification that every module variant served on the authored scenario date.

What is the "War on Terror" era for? Iraq and Afghanistan missions with a **2003–2025 aircraft service-window filter**. This broad preset is not a claim that a particular conflict or deployment lasted through 2025; named scenarios retain their authored dates. Its defining setting is the opposition: there is no enemy air force and no radar SAM; the threat is guns and MANPADS, which is why the transit profile sits higher than

Modern's. If you want MiGs over Iraq, pick Modern instead.

Parking, skins and historical fidelity

Parked aircraft use measured stand directions where survey data exists. Iraq now has surveyed directions at all 20 airfields; other surveyed maps use their own measurements. Unsurveyed stands use a geometric estimate. The Channel and Falklands still need direction surveys. Stand size and direction are separate: a parking stand can have exact size information without a measured direction.

Static skins are selected by aircraft model, nation and era only when the livery name has been verified. Cold War USA F-4 statics use verified USAF skins where available. Other combinations use DCS stock skins; this does not promise an era-specific skin for every aircraft. The wider curated livery collection remains unavailable until its folder names are verified against a DCS install.

Library briefs identify DCS substitutions and what a training mission can measure. For example, the refueling grade measures position and stability; it cannot confirm a fuel transfer. Follow each ride's printed standards and known issues. Historical overlays distinguish sourced boundaries from approximate or illustrative geometry; map-era presets are broad settings, not exact historical reconstructions of every aircraft and installation.

Scenario dates and historical context

Library mission details show an authored **scenario date** and identify the setting as a **historically inspired adaptation** or **fictional exercise**. Expand **Setting, sources & adaptations** before generating. The same context appears in the mission description, Markdown/PDF brief and an additional keyboard page. Published packs use the context supplied with their stored revision; older or externally authored packs may have no historical metadata.

Named settings have their own dates: Proud Phantom uses **10 July 1980**, the fighter arrival date (advance parties arrived earlier); the White Knights checkout uses a 1980 reference day. Sinai's October War setting uses **6 October 1973**, Falklands **21 May 1982**, the expanded Kola NATO exercise **21 June 2024**, and Afghanistan OEF **21 June 2011**, before the base handovers. These are training anchors, not reconstructions of the individual day's sorties.

Known weapon service windows are checked against the actual mission year for player, adversary and carrier strike fits. Unknown service dates remain uncertified; station compatibility does not establish national/operator availability. The aircraft picker still filters by the broader era, so later module variants can remain as disclosed training substitutions.

Historical overlays are references, not automatic routing or violation grading:

- **Berlin:** approximate corridor terminals; the 10,000-ft limit is an exercise rule. Historical altitude and escort permissions were more complex.
- **Nevada:** the 14-vertex R-4808N polygon uses the **1995 FAA boundary**, also retained on earlier-era training missions. Its trigger zone is a bounding circle, not the legal polygon.
- **Syria:** the Euphrates sketch references a **7 February 2018** coalition report. Four approximate points do not establish a precise operational line or its continuous validity; the 2015 flight-safety MOU did not create it.

- **Afghanistan:** the Kabul circle and Helmand rectangle are illustrative.

Operational dates, vertical limits and controlling agencies are unknown.

The Normandy and Marianas WWII presets use broad campaign basing substitutions: Carpiquet and Tinian were not Allied operational bases on the default June 1944 date. Falklands Mount Pleasant is a postwar substitution. Display nationality is distinct from territorial host, visiting operator and game coalition; it does not certify an aircraft roster.

Release identity and the manual

The version beside the title identifies the running release. Reload the page after a deployment to load its latest controls and version. The downloadable User guide uses this same version on its cover. Every release reviews this manual and updates its instructions when behavior, controls or limitations change. The PDF is generated from this document so both copies stay aligned.

Builder reference

ERA

Hard-filters maps, aircraft, statics and air defenses to the period.

World War II (1939-1946)

Cold War (1965-1985)

Modern (2000s+)

War on Terror (2003-2025)

MISSION

What kind of sortie is this? It sets the theater up for you — you can change anything afterwards.

Open tasking
A living theater, nothing assigned

Air-to-air
Enemy fighters up on the threat axis

Strike
Targets in the enemy rear, defended

Close air support
Low, in the guns, over the target

SEAD
Hunt the radars first

Carrier ops
Needs a carrier-capable jet and a coastal map

Training
Range work with the threats turned down

Pick one and this line will tell you exactly what it changed.

MAP

Caucasus
Free terrain

The Channel
Paid terrain

Persian Gulf
Paid terrain

Nevada (NTTR)
Paid terrain

Normandy 2
Paid terrain

Syria
Paid terrain

Sinai
Paid terrain

Marianas
Free terrain

Cold War Germany
Paid terrain

Kola
Paid terrain

South Atlantic
Paid terrain

Afghanistan
Paid terrain

Iraq
Paid terrain

AIR CORRIDORS

open theater — 1 lanes available

Hide

Curated tactical lanes for this map & era. Pick one or more to orient the threat axis and concentrate enemy air defenses & CAP down the lane. None = open theater (free-fly). No player waypoints, ever.

Range 74 Threat Axis

↳ North into the training threat ranges

✦ Enemy: Layered SAM ranges + aggressor CAP

The Builder: choose the theater and era.

SELECT, DON'T SEARCH · WE SET THE STAGE — YOU WRITE THE PLAY

Not affiliated with Eagle Dynamics · page 11

REVIEW

One glance, then build. Any rail item jumps you back to tweak.

Mission readiness

Requires	Nevada (NTTR) · FA-18C_hornet
Your content	Ownership not set. Declare your modules in Library → My DCS content.
Flight	1 human aircraft + 0 veteran AI wingmen (High skill). Single-player.
Departure	Nellis — 233 size-compatible stands before allocation. Static directions: 233/247 stand-specific measurements; other stands use field defaults or geometric estimates.
Equipment	Stores are composed during generation; check Your loadout in the Mission Kit.
Dependencies	AI/support assets and installed module versions are not fully certified; inspect the generated briefing and DCS load warnings. Aircraft counts exclude cockpit crew positions. Consult the authored briefing and module for crew-seat and multiplayer join settings.
Validation	Selection checked · file not built yet · DCS flight unverified. App v1.112.0.

01 MISSION	Modern (2000s+) · Nevada (NTTR)	
02 FLIGHT	blue · Just me · FA-18C · Nellis	
03 OPPOSITION	Moderate · Era standard	
04 AIRFIELDS	US Air Force · 45% fill	
05 SUPPORT & PRESENTATION	Tanker · AWACS · Ambient traffic +4	

[GENERATE .MIZ](#)[Copy share link](#)

Review the recipe before generating your mission kit.