



IT 123 – System Administration and Maintenance

Lab week 2

Dr. Guillermo V. Red, Jr.

Professor

Robinson M. Quinday

Student:



1. Create new VM and attach Iso

The screenshot shows the 'New Virtual Machine' wizard in Oracle VM VirtualBox. The left pane displays a decorative image of a potted plant with a blue flower. The right pane contains the following settings:

- VM Folder: C:\Users\Administrator\VirtualBox VMs
- ISO Image: C:\Users\Administrator\Downloads\ubuntu-26.04.1-live-server-amd64.iso (with a green checkmark icon)
- OS Edition: (empty dropdown)
- OS: Linux (with an x64 icon)
- OS Distribution: Ubuntu
- OS Version: Ubuntu 25.04 (Plucky Puffin) (64-bit)
- ☒ Proceed with Unattended Installation

Below these settings are three expandable sections:

- > Set up unattended guest OS installation (with a red warning icon)
- > Specify virtual hardware
- > Specify virtual hard disk

At the bottom, there are 'Help', 'Finish', and 'Cancel' buttons.

2. Allocate Resources

The screenshot shows the 'New Virtual Machine' wizard in Oracle VM VirtualBox, specifically the 'Specify virtual hardware' step. The left pane displays the same decorative image of a potted plant. The right pane shows the following resource allocation settings:

- > Virtual machine name and operating system
- > Set up unattended guest OS installation
- ✓ Specify virtual hardware
 - Base Memory: A slider bar ranging from 4 MB to 16384 MB, currently set at 2048 MB.
 - Number of CPUs: A slider bar ranging from 1 CPU to 4 CPUs, currently set at 2 CPUs.
 - ☐ Use EFI
- > Specify virtual hard disk



3. Create Virtual Hard Disk

New Virtual Machine

Virtual machine name and operating system
Set up unattended guest OS installation
Specify virtual hardware
Specify virtual hard disk

☒ Create a New Virtual Hard Disk

Hard Disk File Location and Size

C:\Users\Administrator\VirtualBox VMs\UbuntuServer1\UbuntuServer1.vdi

Disk Size 25.00 GB

4.00 MB 2.00 TB

Hard Disk File Type and Format

VDI (VirtualBox Disk Image) ☐ Pre-allocate Full Size
☐ Split Disk Into 2 GB Parts

☐ Use an Existing Virtual Hard Disk File

UbuntuServer.vdi (Normal, 25.00 GB)

☐ Create Virtual Machine Without a Virtual Hard Disk

Help Finish Cancel

4. Enable Networks

UbuntuServer - Settings

Basic Expert

General System Display Storage Audio Network Serial Ports USB Shared Folders User Interface

Search settings

Network

Adapter 1 Adapter 2 Adapter 3 Adapter 4

☒ Enable Network Adapter

Attached to NAT

Name

Adapter Type Intel PRO/1000 MT Desktop (82540EM)

Promiscuous Mode Deny

MAC Address 0800274C3FFB

☒ Virtual Cable Connected

Port Forwarding

Serial Ports

Port 1 Port 2 Port 3 Port 4

☐ Enable Serial Port

OK Cancel Help