

Great Places to Work

Understanding the LSP Quick Guide

Version 0.1

Table of Contents

Introduction	4
What is the LSP?	4
Relevant Standards.....	4
Overview.....	5
Logical Overview.....	5
Zone Overview	6
Simplified Overview	7
Zone Definitions.....	7
Zone Communications	8
Requesting Access	9
RBSDMZ01 Account.....	9
SecureID RSA Token Setup	9
Reset RBSDMZ01 Password	11
SecureFX.....	12
Citrix Plugins.....	12
Accessing the LSP.....	14
Logging on via Citrix.....	14
Logging into LSP in Managed Test Environment	14
File Transfer Overview.....	15
Process Overview.....	15
Setup SecureFX.....	16
Setup SecureFX for LSP in MTE.....	16
File Transfer – Windows.....	17
Copy Files into the LSP.....	17
PCI - DSS.....	18
What is it?.....	18
Why is compliance important?	18
What is Card Data?.....	19
Backup Infrastructure	21
LSP Backup Infrastructure Overview.....	21
Autosys	22
Autosys Scheduling.....	22
How do I get Autosys.....	22
Active Directory	26
Strategic Domains.....	26

Default Domains	26
DNS Domain Suffix	26

Introduction

What is the LSP?

The Layered Scalable Perimeter (LSP) is perimeter infrastructure that replaced the Secure Server Infrastructure (SSI). The aim is to make a network perimeter environment more flexible and scalable while providing an environment that allows for greater use of shared resources.

Any network not owned and controlled by RBS is considered external. LSP provides secure access to and from external networks, such as the Internet and other third-party resources. It is designed to be flexible in its approach to the services that are hosted, whilst maintaining the perimeter security of the Bank and its strategic partners. It provides a number of services:

- Access to external resources/networks
- Managed security components; Network firewall, Web application Firewall, IDS
- Hosting of server components and other devices involved in communication with external networks
- Access to shared Applications and Management functions

The LSP allows services provisioned into the perimeter to share common elements. This is to save on server duplication; the main shared services will be management and middleware servers. Each function within the LSP has been allocated a zone.

Relevant Standards

This guide is to give a general understanding of the LSP. For more detailed information please consult the relevant Standards below and also the links throughout the document.



Deploying Services in the LSP – STN-483

http://www.manufacturing.rbsgrp.net/gtip/GIS/standards/doc_library/stn-search-numbers.asp?number=483&submit=Search+standards+by+number



Deploying Components in the LSP – STN-484

http://www.manufacturing.rbsgrp.net/gtip/GIS/standards/doc_library/stn-search-numbers.asp?number=484&submit=Search+standards+by+number



LSP Network Address Translation – STN-485

http://www.manufacturing.rbsgrp.net/gtip/GIS/standards/doc_library/stn-search-numbers.asp?number=485&submit=Search+standards+by+number




LSP Network Infrastructure Deployment and Scaling – STN-486

http://www.manufacturing.rbsgrp.net/gtip/GIS/standards/doc_library/stn-search-numbers.asp?number=486&submit=Search+standards+by+number

Overview

Logical Overview



Zones 2, 4, 5 & 6 form the perimeter structure. Zone-2 and Zone-4 act as a border between the internal and external networks. Zones 5 and 6 host shared components.

Each of these perimeter zones is comprised of DMZs that host servers. In the externally accessible Zones 2 & 4 each DMZ will contain only devices from one service. Sharing of DMZs for newly deployed services will not be permitted.

Zones 5 & 6 contain shared components that are accessible from other DMZs, such as Websphere applications and management servers.

Zones 5 & 6 are not accessible from the external zones. As per the above diagram, only Zones 2 & 4 are accessible from external zones. Zone-2 communicates with the Internet and Zone-4 communicates with Third-Parties.

Zone Overview

Zone-1 Internet

Any device that interacts with RBS networks via the Internet is in Zone-1. Zone-1 is untrusted.

Zone-2 Internet Facing

Zone-2 is the only place where devices can reside if they are directly accessible from the internet, or if they access resources on the internet. It contains the first tier of devices in all Internet based communication, such as web servers, web browsing proxies, internet mail relays, internet VPN terminators, etc.

Servers in Zone-2 are attached to multiple DMZs with specific purposes. For example they will have an interface on an 'external' DMZ that external clients can access. In addition they will have interfaces connecting to DMZs providing access to the internal, application and management zones as required.

Zone-3 Third-Party

Any device at a Third-Party network is in Zone-3. Zone-3 is un-trusted.

Zone-4 Third-Party Facing

Zone-4 is the first tier of communication with all third-parties. A device should be placed in Zone-4 if it interacts directly with an external Third-Party resource. Zone-4 also has a split front and back design, with servers having external interfaces that third-parties can access and internal interfaces that access internal and other zones.

Zone-5 Application

Zone-5 is equivalent to a second tier for external facing applications. It contains application servers and any other device considered second tier or directly involved with the application processing for a service. It is a shared zone and can provide services to third-party and internet applications. Zone-5 is not accessible from the external zones.


Zone-6 Management

A device should be placed in Zone-6 if it provides management or support services to other perimeter components (i.e. not directly involved in the information processing of the service itself, but required to manage or maintain other components. An example would be an Active Directory server). Zone-6 is also shared and can manage devices in all zones

Corenet/Internal Network (aka Zone-7)

All internal RBS networks and devices constitute Zone-7, this is commonly referred to as corenet or the Internal Network. It is the third tier where data sources such as mainframes and databases reside.

Simplified Overview



Zone Definitions

- Zone 1 – The Internet – All Internet connections are terminated in this zone
- Zone 2 – Internet facing DMZ – All Internet facing server are positioned in this zone
- Zone 3 – 3rd Party External network – All 3rd party connections are terminated in this zone
- Zone 4 – 3rd Party facing DMZ – All 3rd party facing servers are hosted in this zone
- Zone 5 – Application – All shared application servers are in this zone
- Zone 6 – Management – All device and server management is handled in this zone
- Zone 7 - Internal Network – This is the RBSG internal network (Holi)

Zone Communications

To ► From ▼	Zone-1 Internet	Zone-2 Internet Facing	Zone-3 Third-Party	Zone-4 Third-Party Facing	Zone-5 Applications	Zone-6 Management	RBS Internal Network (aka Zone-7)
Zone-1 Internet	No	Yes	No	No	No	No	No
Zone-2 Internet Facing	Yes	Yes	No	No	Yes	Yes	Yes
Zone-3 Third-Party	No	No	No**	Yes	No	No	No †
Zone-4 Third-Party Facing	No	No	Yes	Yes	Yes	Yes	Yes
Zone-5 Applications	No	Yes	No	Yes	Yes	Yes	Yes
Zone-6 Management	No	Yes	No	Yes	Yes	Yes	Yes
RBS Internal Network (aka Zone-7)	No	Yes	No †	Yes	Yes	Yes	Yes

Table 1 – Zone Communication

Yes = Permitted

No = Not permitted

** Access controls must be deployed to ensure one Third-Party cannot influence communication with another.



Note that communication between third parties and the internal network is permitted provided that:

- The communications are file transfers using Connect:Direct Secure +
- It uses private telecomms links (with or without VPN, into Zone 4) or internet (only with VPN) into Zone 2

Using the table as a guide you can determine, for example, that any RBS components communicating directly with the Internet must be placed in Zone-2, and any RBS components communicating with Third-Parties must be placed in Zone-4. All non-internet based 3rd party connectivity takes place out zone 3 (i.e. managed VPN service, such as MPLS, to 3rd party). For RBS internal user access to the 3rd party hosted service, RBS internal users (aka "Zone-7") need to come via an intermediate device (e.g. proxy) in zone 4 and then out to the 3rd party via zone 3. (But see note above.) If the device does not interact directly with external networks, or provide management or serve data directly to components that do interact directly

Requesting Access

RBSDMZ01 Account

In order to login to the LSP you will require an account in the RBSDMZ01 domain



Requesting account via SLX

http://slx.web.rbsgrp.net/Content/LanAdmin/Forms/Network/Form_NewAccount.aspx

Select Additional Account - (For users that already have a Primary Account)

Account needs created on the **RBSDMZ01** domain

SecureID RSA Token Setup

As well as an account on RBSDMZ01 you will also need a EUROPA SecureID token.



You can request your SecureID token is setup while you are waiting on your RBSDMZ01 account. The account and SecureID token requests are not dependent on each other.



Requesting SecureID token setup

http://slx.web.rbsgrp.net/Content/LanAdmin/Forms/RemoteAccess/Form_RemoteAccess.aspx?type=secure

Platform details

[View help for this section \(popup\)](#)

* Is the Users' Department on RBS Group VDI (Virtual Desktop) - [What is this? \(Popup\)](#)

☒ Yes

☐ No

* Select the environment/platform the request will be actioned on

RBS Group VDI (Virtual Desktop) 

Next

Service Requirement is LSPNTSAC01

Request Details

- * Request Type
 - ☒ Add Dial-In or Secure Environment Access
 - ☐ Remove Dial-In or Secure Environment Access
- * Add or Remove VCS Remote Access?
 - ☐ Add VCS Remote Access
 - ☐ Remove VCS Remote Access
- * Does the user require complete removal from Ace Server?
 - ☐ Yes
 - ☐ No
- * Service Requirement
 - LSPNTSAC01
- * Is VDI Printing Required?
 - ☐ Yes
 - ☐ No

Back

Next

On this form you can also request a SecureID token if you do not have one

Remote Access - Additional Information

- * Do you require a SecureID token with this request - [What is this? \(Popup\)](#)
 - ☒ Yes, I require a token with this request
 - ☐ No, A token is not required with this request



You will require a Group SecureID token and not an FM one.

Reset RBSDMZ01 Password

Once your account is created you will need to reset the password to use it



Reset RBSDMZ01 password

http://slx.web.rbsgrp.net/Content/Passwords/Forms/Screener_Password.aspx?type=ntxp



Important – Select NO below so that RBSDMZ01 is available on the list of domains on the next screen

Are you on one of the below domains?

- If both the authoriser(s) AND the user for this request ALL log on to the SAME domain from the list below, please select 'Yes'.
- If your domain is not listed, OR if not all users log on to the same domain, please select 'No'.
- If you are unsure what domain you log on to, please run our [domain tester page](#) to find out.

* Please Choose:

- ☐ Yes
☒ No

Domain List

[View help for this section \(popup\)](#)

- CC_MASTERDOMAIN
- CCTESDOMAIN
- COUTTSUK
- EUROPA
- FM
- GFRNT
- IFS_Live
- Investments
- LFCI
- LOMBANKDM
- LOMBARD
- OBB
- RBSRES01
- UBM
- UBR
- UKGFLS

Please Note: The RBS Domain does not include RBS01, 02, 03, 04

SecureFX

To allow you to SFTP files from your Windows PC to the LSP you will need an SFTP client. SecureFX is available via iProcurement

XP Desktop \ VDI
Install COE00688



Request via iProcurement

<https://fincm.web.rbsgrp.net/>

VCS \ VCS2 \ VCSe
Request VOE00688 - SecureFX



Request via iProcurement

<https://fincm.web.rbsgrp.net/>

Citrix Plugins

In order to access the LSP you will need to login to a Citrix Netscaler server to be able to then access the support applications and tools.



Logon to LSP via Citrix

<https://lspaccess.gslb-lsp.web.rbsgrp.net/vpn/index.html>

During the logon process the Endpoint Analysis Plugin will check your local workstation. If this fails you will not be able to logon.



Access Gateway™
Endpoint Analysis



Citrix Endpoint Analysis is scanning your system.

In order to access specific corporate resources, an endpoint analysis scan is required.

Information about your system is sent to your corporate network for further evaluation.

Do you wish to run the scan?

Yes

No

Always

XP Desktop \ VDI

Install COE05763



Request via iProcurement

<https://fincm.web.rbsgrp.net/>

VCS \ VCS2 \ VCSe

Added via Application Self Service – search for LSP

RBOS_CitrixConfigLSP_1.0_x86_APV07455_v1.0

rAPV RBOS CitrixConfigLSP 1.0 x86 v1.0


Accessing the LSP

Logging on via Citrix



Logon to LSP via Citrix

<https://lspaccess.gslb-lsp.web.rbsgrp.net/vpn/index.html>



The screenshot shows a login window titled "Welcome". The text inside reads: "Welcome to the Royal Bank of Scotland Citrix XenApp farm.", "Please enter your user credentials and domain name to login.", and "For support please call Serviceline." On the left is a blue padlock icon. On the right are three input fields labeled "User name:", "Windows Password:", and "SecurID PIN+Passcode:". Below these fields is a "Log On" button.

Logging into LSP in Managed Test Environment




Logon to LSP in MTE

<https://kpordmz.gdlb-lsp.web.rbsgrp.mde/vpn/index.html>



File Transfer Overview

Process Overview



On **RESFTP.server.rbsgrp.net** each team has their own folder within Teamshares
Each Team Folder has PUSH and PULL subfolders within them

Each team also has their own PUSH \ PULL Scripts




Setup SecureFX

Launch the SecureFX application. Navigate to File -> Connect -> New Session. Create a new session with the below details:

Protocol: SFTP
Host: RESFTP.server.rbsgrp.net
Port: 22
Username: EUROPA\<RACF_ID>
Password: Blank
Initial Directory: Blank

Click Finish to create the session. Define a Session name and a brief description for future reference.

Right click on the session name and choose properties. Highlight SSH2 and change MAC to SHA1 (See below). Other fields can be left with their default values.



SecureFX is now setup and you will be prompted for your password on connection

Setup SecureFX for LSP in MTE

Launch the SecureFX application. Navigate to File -> Connect -> New Session. Create a new session with the below details:

Protocol: SFTP
Host: 11.152.23.252
Port: 22
Username: M01EUROPA\<RACF_ID>
Password: *Blank*
Initial Directory: *Blank*
Finish


File Transfer – Windows

Copy Files into the LSP


1. Copy files from your PC using SFTP client (SecureFX, WinSCP etc) to Un-trusted SFTP server
RESFTP.server.rbsgrp.net

Copy the files to Teamshares**YourTeamFolder**\Pull folder

2. Login to the LSP and from within the Worldpay folder run LSP sFTP



3. Execute the relevant PULL script for your team.



4. From your server within the LSP use the following methods to access your files
Windows – Map to \\GBMLVLSPFT01\Teamshares**YourTeamFolder**\Pull folder

PCI - DSS

What is it?

PCI DSS is the Payment Card Industry Data Security Standard.

PCI DSS is the global data security standard adopted by the payment card brands for all entities that process, store or transmit cardholder data and/or sensitive authentication data. It consists of steps that mirror security best practices. It is a list of controls and requirements developed by the card schemes (Visa, Mastercard etc) that define how we should be handling card data security.

PCI DSS is a minimum set of requirements for protecting card data, and may be enhanced by additional controls and practice to further mitigate risks.



RBS - PCI DSS Guidance

<https://www.securityzone.rbs.com/documents/PCI%20DSS%20Mandatory%20Procedure-Final1.1.pdf>



PCI DSS 3.2 Complete document

https://www.pcisecuritystandards.org/documents/PCI_DSS_v3-2.pdf?agreement=true&time=1482228610876



PCI DSS Quick reference Guide

https://www.pcisecuritystandards.org/documents/PCIDSS_ORGv3_2.pdf?agreement=true&time=1482228611043

Goals	PCI DSS Requirements
Build and Maintain a Secure Network and Systems	1. Install and maintain a firewall configuration to protect cardholder data 2. Do not use vendor-supplied defaults for system passwords and other security parameters
Protect Cardholder Data	3. Protect stored cardholder data 4. Encrypt transmission of cardholder data across open, public networks
Maintain a Vulnerability Management Program	5. Protect all systems against malware and regularly update antivirus software or programs 6. Develop and maintain secure systems and applications
Implement Strong Access Control Measures	7. Restrict access to cardholder data by business need to know 8. Identify and authenticate access to system components 9. Restrict physical access to cardholder data
Regularly Monitor and Test Networks	10. Track and monitor all access to network resources and cardholder data 11. Regularly test security systems and processes
Maintain an Information Security Policy	12. Maintain a policy that addresses information security for all personnel

Why is compliance important?


- **Reducing fraud for our customers** – A key objective of PCI DSS is to reduce payment card fraud. Becoming compliant with PCI DSS will increase the security of our systems and business processes and help to reduce card fraud.

- **Contractual obligation** - As the bank uses and handles cards with the Visa and MasterCard logos, we have a contractual obligation with these card schemes to comply with PCI DSS.
- **Customer confidence** - Our customers expect that we handle their information securely. Protecting customers' card data is a fundamental part of how we serve our customers. Security only becomes headline news when it goes wrong and when it goes wrong it can be devastating for our customers.
- **RBS' reputation** - A breach of card data due to non compliance with PCI DSS would cause serious harm to our reputation. This could lead to:
A loss of confidence in our brand, impacting negatively on our plan to rebuild public confidence in the bank;
Customers switching to other banks; and
A drop in our share price.

What is Card Data?

Primary Account Number (PAN). This is the long card number on the front of the card. If the PAN is stored, other card information such as cardholder name and expiry date become in scope when stored with the PAN.

Sensitive Authentication Data (SAD). This includes the magnetic stripe/chip data, security code (CAV2, CVC2, CVV2 or CID) or the card PIN.



Cardholder Data includes:	Sensitive Authentication Data includes:
• Primary Account Number (PAN)	• Full magnetic stripe data or equivalent data on a chip
• Cardholder Name	• CAV2/CVC2/CVV2/CID
• Expiration Date	• PINs/PIN blocks
• Service Code	

**PCI DSS 3.2**

https://www.pcisecuritystandards.org/documents/PCI_DSS_v3-2.pdf?agreement=true&time=1482228610876

**PCI Security Standards**

<https://www.pcisecuritystandards.org>

**PCI DSS Quick reference Guide**

https://www.pcisecuritystandards.org/documents/PCIDSS_ORGv3_2.pdf?agreement=true&time=1482228611043

**RBS - PCI DSS Guidance**


<https://www.securityzone.rbs.com/documents/PCI%20DSS%20Mandatory%20Procedure-Final1.1.pdf>

**PCI DSS Support Function**

FM-016274@rbos.co.uk

Backup Infrastructure

LSP Backup Infrastructure Overview



Storage Projects

Implementation - Technical Resourcing - Edinburgh Storage



Storage Engineering

GIS SA&E Storage Engineering Team



Storage Support

~ MS Distributed Storage Services - Midrange Tape

Autosys

Autosys Scheduling

Autosys is a centralised, cross-platform, event driven job scheduling tool. These jobs can be defined to run on any configured machine that's connected to the network.

A job is any single command, executable, script or batch file. Each job definition contains information about when and where each job should be run.

Within RBS Autosys is used to schedule jobs to the following operating systems

Solaris 8 9 10

Red Hat Enterprise Linux RHEL – 4 5 6

Windows 2003, 2008 and 2012

AIX 5.3, 6.1 and 7.1

Solaris 8 and 9, RHEL 4 and Windows 2003 will be supported on best endeavours basis as vendor support is no longer available for the agents running on the unsupported OS's

Autosys must not be used to schedule tasks on workstations and should not be used to schedule tasks where purpose is to check system performance.

Autosys is the strategic tool for all distributed workload scheduling. It should not be used for scheduling to distributed servers which are dependent on CA-7 mainframe batch schedules.

Autosys in the LSP

Instance – EP1

Version – r11.3.6

Scheduling Region – Edinburgh – LSP Only

Environment – Production



Further Reading – STN-708

http://www.manufacturing.rbsgrp.net/gtip/GIS/standards/doc_library/stn-search-numbers.asp?number=708&submit=Search+standards+by+number

How do I get Autosys

Prerequisites

Your application must have a valid GEL entry if you wish to use AutoSys to schedule jobs.

All AutoSys job names have a 3 character application prefix which will be assigned by Batch Scheduling Services upon request and will be based on the GEL entry. Raise a 'New Application Request' iTask for DCS Batch Scheduling to have your prefix assigned.

This prefix identifies your jobs to the Batch Services Infrastructure Team and the TAC and is used for creating user group and filters within iXp.

A Roma rota must also exist for your application. This is shown in the 'Rota' tab when viewing your application in GEL. The Roma rota will be used by the TAC to identify what action to take when alerts

are received.

For further information on Roma see the ROMA entry in GEL.

Installation

Unix - For Unix and Linux servers, the Unix support team will install the agent, this is in the form of a Solaris package or a Red Hat RPM.

For Markets application, you can request an agent install by raising an iTask to the DCS Unix team.

For production instances you should raise a GEL Change Request against your own application and the iTask specifying which agent is required SP2 or SP4.

For TS applications, you can request an install by contacting Unix Projects team.

No reboot is required and AutoSys jobs can run as any valid Unix or Linux account which has access to the server after the as-owner rules have been updated in EEM and iXp.

Windows

FM C&IB Applications

Windows agent installs within the FM Domain are performed by the Batch Scheduling Services (BSS)/Batch Services Infrastructure.

For Markets application, an agent install can be requested by raising an 'Agent Install (Windows)' iTask to the DCS Batch Scheduling queue. For production instances you should raise a GEL Change Request against your own application and add the iTask specifying which agent is required SP2 or SP4. For new applications you can include the install request in the 'New Application Request' iTask as mentioned above.

Specifically for Windows, prior to the agent install the Batch Services Infrastructure team will have an 'sca' (Server Console Application) account created or, if it already exists, will request access for the account to the servers on which the agent is to be installed. This request is raised in the Customer Request System and typically takes 5 working days to complete. The 'sca' account is owned by the Batch Services Infrastructure team and used to install the agent, troubleshoot any AutoSys issues and schedule jobs to the server. These account details are held, encrypted, in a secure CyberArk safe and in the AutoSys database. The password will not be made available to application teams.

If you require separate 'sca' accounts for production and non-production environments you should specify this in your iTask.

TS Applications

All Windows agent installs within the MTE (Managed Test Environment) should be requested under a project/MTR (Managed Test Record).

Depending on the domain the TS/GROUP Application servers are in will determine who can perform the Windows Agent install and also whether or not you will require additional firewall ports to be opened up between the application servers and the relevant AutoSys servers.

RBSRES01/M01RBSRES01 – Production/TEST HOLI/Corenet Domains, installs are performed by the Batch Scheduling Services (BSS)/Batch Services Infrastructure.

RBSDMZ01/M01RBSDMZ01 – Production/TEST LSP Domains, this will require the Windows project

resource to copy the agent package to the relevant servers and then the install can be performed by the Batch Scheduling Services (BSS)/Batch Services Infrastructure.

For TS applications, service-xxxautosys accounts are used

Specifically for Windows, prior to the agent install the Batch Services Infrastructure team will have a service-xxxautosys@domain account created or, if it already exists, will request access for the account to the servers on which the agent is to be installed. Again, depending on which domain the servers are in will determine how the request is raised and how long it takes. The 'servicexxxautosys@domain' account is owned by the Batch Services Infrastructure team and used to install the agent, troubleshoot any AutoSys issues and schedule jobs to the server. These account details are held, encrypted, in a secure CyberArk safe and in the AutoSys database. The password will not be made available to application teams.

Autosys Firewall Ports

Firewall ports are required to be opened between the AutoSys EP1 scheduler servers and each agent machine within the LSP (RBSDMZ01):-

Server	IP Address	Port	Direction
mm2asyn01a.server.rbsgrp.net (AutoSys EP1 Primary scheduler)	11.247.129.77	7500 7507 7520	Bi-Directional
mg1asyn01b.server.rbsgrp.net (AutoSys EP1 Secondary scheduler)	11.247.129.83	7500 7507 7520	Bi-Directional

Firewall ports in the MTE (M01RBSDMZ01) have already been opened from the AutoSys ST1 scheduler servers:-

Server	IP Address	Port	Direction
st1asyn01f.server.rbsgrp.ppe (AutoSys ST1 Primary scheduler)	11.155.239.45	7500 7507 7520	Bi-Directional
st1asyn03f.server.rbsgrp.ppe (AutoSys ST1 Secondary scheduler)	11.155.239.41	7500 7507 7520	Bi-Directional


to the following subnets:-

- 11.151.0.0 /16 (infoBlox Testing)
- 11.152.0.0 /16 (KPOR MDE A)
- 11.153.0.0 /16 (KPOR MDE B)
- 11.154.0.0 /16 (KPOR PPE A)
- 11.155.0.0 /16 (KPOR - LSP)
- 11.156.0.0 /16 (STONE MTE)
- 11.157.0.0 /16 (STONE)
- 11.158.0.0 /16 (STONE-MDE)
- 11.159.0.0/16

- 10.200.0.0/16
- 10.221.0.0/16
- 10.222.0.0/16

Active Directory

Strategic Domains



Default Domains

LSP Service	Domain (Default)
LOB Application	OCISSIA
Shared Infra \ PCI-DSS	RBSDMZ01.NET
ATM Clients	RBSGATM.NET

DNS Domain Suffix

Zone 2 Management	RBSDMZ01.NET
Zone 2 Outer	z2o.RBSDMZ01.NET
Zone 2 Inner	z2i.RBSDMZ01.NET
Zone 2 Access	z2.RBSDMZ01.NET
Zone 4 Management	RBSDMZ01.NET
Zone 4 Outer	z4o.RBSDMZ01.NET
Zone 4 Inner	z4i.RBSDMZ01.NET
Zone 4 Access	z4.RBSDMZ01.NET
Zone 5 Management	RBSDMZ01.NET
Zone 5 Access	z5.RBSDMZ01.NET
Zone 6	RBSDMZ01.NET