



STONEWEAVE

Version Control

Server User Guide

Complete guide for all server users

June 2026 V1.0

1. Introduction

Stoneweave Version Control is a file versioning system designed for engineering and industrial environments. It gives your team a safe, structured way to track every change to any file - PLC programs, CAD drawings, documents, spreadsheets, and more.

Think of it like tracked changes in Microsoft Word, but for any type of file. Every time someone makes a change, the old version is kept. You can view, compare, and restore any previous version at any time.

Key Concepts

- Project - a top-level container (e.g. 'Conveyor Line 3' or 'Building A Controls')
- Area - a section within a project (e.g. 'Electrical', 'Safety Systems', 'Mechanical')
- File - the actual document or program being tracked
- Version - a complete snapshot of a file at a specific point in time
- Check Out - reserving a file for editing so nobody else can modify it at the same time
- Check In - uploading the edited file, creating a new version, and releasing it for others

User Roles

Role	Permissions
Operator	View files and history. Check out and check in files. View the audit log.
Supervisor	All operator actions, plus: revert to previous versions, edit version details, create and manage projects and areas.
Admin	All supervisor actions, plus: manage users, configure all settings, force-unlock checked-out files, manage backups, and clear the audit log.

2. Logging In

1. Open your web browser and go to the server address (e.g. <http://192.168.1.105:5000>).
2. Enter your username and password.
3. Tick Remember me to stay logged in between browser sessions.
4. Click Log In.

Note

If Two-Factor Authentication (2FA) is enabled on your account, you will be asked for a 6-digit code from your authenticator app after entering your password.

Forgotten Password

1. Click Forgot password? on the login page.
2. Enter your email address and click Send Reset Link.

3. Check your email and click the link to set a new password.

Note

Password reset by email requires the administrator to have configured the SMTP email settings. If the email does not arrive, ask your admin to reset your password manually.

3. The Dashboard

The dashboard is the first screen after login. It gives an instant overview of the system.

- Stats strip (top) - total projects, tracked files, files checked out, files available
- Checked Out panel - every file currently checked out: who has it, which workstation, and how long ago
- Recent Activity panel - the last 10 actions across the system (check-ins, check-outs, new additions)
- Projects table - all projects with file counts. Click a project name to open it.

Tip

Example: at a glance you can see Sarah has Line3_Safety.acd checked out on her laptop and has had it for 2 hours.

4. Projects and Areas

Files are organized into Projects, and each project can be divided into Areas for easier navigation.

Browsing Projects

1. Click Projects in the left sidebar.
2. Each row shows the project name, category badge, file counts, and how many files are checked out.
3. Click a project name to open it.

Creating a New Project (Supervisor / Admin)

1. Click New Project in the sidebar.
2. Enter a project name and select a category.
3. Add a description if useful, then click Create Project.

Areas and Sub-Areas

Within a project you can create areas to group related files (e.g. 'Electrical', 'PLC Programs', 'HMI Screens'). Areas can be nested to create sub-areas. When viewing a project you can switch between:

- Area View - files grouped by area, displayed as an expandable tree
- Folder View - flat list with breadcrumb path labels

5. Browsing Files

1. Click Files in the left sidebar to see all files across all projects.
2. Use the filter bar to narrow by project, or search by filename.
3. Each file shows its current status:
 - Green - Available (nobody has it checked out)
 - Orange lock icon - Checked Out by [Name] (shows who has it)

6. Adding a New File to Version Control

Any logged-in user can add a file. Once added, every future change is versioned automatically.

1. Click Add File in the top-right area or in the sidebar.
2. Select the project this file belongs to.
3. Optionally select an area within that project.
4. Upload the file by clicking Choose File.
5. Write a description of this initial version.
6. Leave Change Type as Initial.
7. Click Add File.

Tip

The file is now at Version 1. All future changes create a new version - the original is never overwritten.

Note

Certain file types (e.g. .exe, .bat) are blocked for security. Contact your admin if you need to track an unusual file type.

7. The Core Workflow: Check Out → Edit → Check In

Stoneweave uses a check-out / check-in model - like borrowing a library book. Only one person can edit a file at a time. Others can still view and download the latest version, but cannot check it out while you have it.

Step 1 - Check Out

1. Find the file in the Files list or via a project.
2. Click Check Out.
3. Enter a reason for the check-out (required).

4. Optionally enter your workstation name - this helps others know which PC has the file.
5. Click Check Out & Download. The file saves to your PC automatically.

Tip

Example: John finds Line3_Safety.acd, clicks Check Out, enters 'Updating safety relay logic per ECR-142', and downloads the file.

Step 2 - Edit the File

Open the downloaded file in your software (Studio 5000, TIA Portal, AutoCAD, Microsoft Office, etc.). Make your changes and save the file using the same filename.

Step 3 - Check In

1. Return to the Stoneweave file page.
2. Click Check In.
3. Upload the modified file.
4. Select the Change Type (see table below).
5. Write a Change Description explaining what you changed and why.
6. Optionally add a Work Order / Reference, a Version Label, and a Change Document (e.g. a PDF change sheet).
7. Click Check In.

Tip

A new version is created. The file is immediately available for others to check out.

Change Types

Change Type	When to Use
Initial	First upload of a new file
Revision	New feature or significant update
Correction	Fixing an error or bug
Maintenance	Minor update, comment cleanup, or formatting change
Emergency	Urgent fix applied directly to a live system
Rollback	Reverting to a previous version
Testing	Temporary test version - not for production
Approval	Formally signed-off and approved version
Other	Anything that does not fit the above

Writing a Good Change Description

Tip

State WHAT changed and WHY. Reference specific rungs, sheet numbers, or tag names. Mention whether it has been tested. Include any work order or ECR number.

Good example: 'Updated rung 0045 on Conveyor_Safety.acd - added E-stop bypass confirm relay per ECR-142. Tested on simulator, ready for live commission.'

Cancelling a Check-Out

If you checked out a file but no longer need to make changes, click Cancel Checkout on the file page. No new version is created and the file is immediately available again.

Warning

Any local edits you made will not be saved to the system. Check in first if you want to keep your changes.

8. Viewing Version History

Every file has a complete, permanent history of every version ever created.

1. Open the file from the Files list or a project page.
2. Scroll down to the Version History section.

For each version you can see: version number, label, date, author, workstation, change type, description, file size, and checksum.

Two History Views

- Table view - chronological list, easy to scan and filter
- Flowchart view - visual diagram showing the progression from first version to latest

Filtering

Use the filter bar above the history to search by keyword, or filter by change type or project phase.

Downloading a Specific Version

1. Click any version row to open the version detail page.
2. Click Download vX to download that specific version.

Note

Downloading an old version does not change the system - it just gives you a local copy. To make an old version the current working copy, use Revert (below).

9. Reverting to a Previous Version (Supervisor / Admin)

If a file has been incorrectly changed, a supervisor or admin can restore an earlier version.

1. Open the file and scroll to Version History.
2. Find the version you want to restore and click Revert.
3. Enter a reason for the revert and confirm.

Tip

A new version is created that is identical to the old one. History is never deleted - everything is preserved.

Example: v7 contained an error. The supervisor reverts to v6. The system creates v8, identical to v6.

10. Project Phases

Versions can be tagged with a project phase to record which life cycle stage the work was at. Common phases include:

- Development - work in progress, not yet approved
- Approved - formally signed off for use
- Commission - in use during site commissioning
- Handover - final version handed to the customer

Select a phase during check-in. You can then filter version history to show only versions from a specific phase. Phases are fully configurable by admins in Settings → Categories.

11. The Audit Log

Every action in the system is automatically recorded. The audit log provides a complete record of who did what and when.

1. Click Audit Log in the left sidebar.
2. Use the filter bar to narrow by action type, user, project, or date range.

Per-File Log

On any file's detail page, scroll to the bottom to see the audit log for that file only.

Exporting the Audit Log

- CSV export - available to all users
- Excel (.xlsx) and PDF export - Premium licence only

12. Your Profile and Appearance

1. Click your name in the top-right corner.
2. Select Profile to view your account details.
3. Click Edit Profile to change your name, email, or password.

Customising the Appearance

Each user can choose their own theme and font settings. Changes only affect your account.

Setting	Options
Theme	Dark, Light, Golden Breeze, Dracula, Nord, Solarised
Interface Font	System Default, Arial, Times New Roman, Calibri, Georgia, Fraunces
Font Size	13 px, 14 px, 15 px, 16 px
Bold Text	On / Off
Sidebar Style	Glass (translucent) or Solid
Custom Accent Colour	Colour picker - overrides the theme's default accent colour

13. User Management (Admin Only)

Adding a User

1. Click Users in the left sidebar.
2. Click Add User.
3. Fill in the name, username, email address, role, and initial password.
4. Click Save.

Disabling a User

Rather than deleting an account - which would affect the audit trail - it is best practice to disable accounts when someone leaves the team. Disabled accounts cannot log in but their history is fully preserved.

Force Unlock (Admin Only)

If a file is stuck checked out because the user is unavailable, an admin can release it.

1. Open the file's detail page.
2. Click Force Unlock.
3. Confirm the action.

Warning

Any unsaved edits on the user's local PC will be lost. Use this only when the user is genuinely unavailable and you cannot wait.

14. Admin Settings Overview

The Settings page (admins only - sidebar → Settings) has six tabs:

Tab	What You Can Configure
Appearance	Themes, fonts, font size, bold toggle, sidebar style, custom accent colour
Storage	Data directory path, configuration file location
Security	HTTPS/TLS, SMTP email, Active Directory (LDAP), 2FA and API keys, active sessions and login history
License	View tier (Free / Premium), activate a licence key, view Machine ID
Categories	Project categories, file type categories, change types, project phases - all fully customisable
Updates	Current and latest version, check for updates, install updates, auto-update toggle

Backup and Automatic Backup

The Backup page (sidebar → Backup) shows storage statistics, database and file paths, and provides backup tools.

- Download Backup - creates a ZIP file of the entire database and all file versions (Premium)
- Automatic Backup - configure a scheduled backup to a folder of your choice (Premium)

To configure automatic backup:

1. Enable the Automatic Backup toggle.
2. Enter the full path to the destination folder.
3. Choose a frequency: Daily, Weekly, Fortnightly, Monthly, or Yearly.
4. Set the time of day (24-hour format).
5. For weekly / fortnightly: select the day of the week. For monthly: select the day of the month.
6. Click Save Auto-Backup Settings.

The Next scheduled backup date and time is shown automatically below the form.