Cisco Packet Tracer - C:\Users\jaswa\OneDrive\Desktop\assignment.pkt

File Edit Options View Tools Extensions Window Help

Logical | Physical | x: 1717, y: 451 | Root | 03:45:00



Time: 00:07:20 | Realtime | Simulation

Router-PT

Scenario 0 | New | Delete | Toggle PDU List Window

Fire	Last Status	Source	Destination	Type	Color	Time(sec)	Periodic	Num	Edit	Delete
	Successful	PC2	PC1	ICMP		0.000	N	0	(edit)	(delete)
	Successful	PC1	PC0	ICMP		0.000	N	1	(edit)	(delete)

19°C Mostly sunny | Search | ENG IN | 18:12 16-04-2026

Cisco Packet Tracer - C:\Users\jaswa\OneDrive\Desktop\assignment.pkt

File Edit Options View Tools Extensions Window Help

Logical | Physical | x: 1523, y: 414 | Root | 05:07:30



Time: 00:10:00 | Realtime | Simulation

IR1101

Scenario 0 | New | Delete | Toggle PDU List Window

Fire	Last Status	Source	Destination	Type	Color	Time(sec)	Periodic	Num	Edit	Delete
	Successful	HQ PC	C PC	ICMP		0.000	N	0	(edit)	(delete)

News for you
LeT co-founder...

Search

ENG
IN

18:14
16-04-2026

Cisco Packet Tracer - C:\Users\jaswa\OneDrive\Desktop\assignment.pkt

File Edit Options View Tools Extensions Window Help

Logical | Physical | x: 924, y: 539



Time: 00:12:15

IR1101

Router 1

Physical | Config | CLI | Attributes

IOS Command Line Interface

```
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up

03:18:31: %OSPF-5-ADJCHG: Process 1, Nbr 192.168.23.1 on FastEthernet0/1 from LOADING to FULL,
Loading Done

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to down

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up


Router>enable
Router#
Router#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#interface FastEthernet0/1
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet1/0
Router(config-if)#ip address 192.168.13.1 255.255.255.252
Router(config-if)#shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet1/0, changed state to administratively down

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to down
no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet1/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up

%DUAL-5-NBRCHANGE: IP-EIGRP 100: Neighbor 192.168.13.2 (FastEthernet1/0) is up: new adjacency

Router(config-if)#interface FastEthernet1/0
Router(config-if)#ip address 192.168.13.1 255.255.255.0
Router(config-if)#
%DUAL-5-NBRCHANGE: IP-EIGRP 100: Neighbor 192.168.13.2 (FastEthernet1/0) is down: interface down

%DUAL-5-NBRCHANGE: IP-EIGRP 100: Neighbor 192.168.13.2 (FastEthernet1/0) is up: new adjacency
```

Copy | Paste

Sunset 6:39 pm | Search | ENG IN | 18:17 16-04-2026