
NP	Networks and Protocols (NP)	Prof. Dr. A. Grebe
CCNA SRWE	Switching, Routing, and Wireless Essentials (SRWE)	

CCNA SRWE Lab 1 Homework Deadline: 25.1.2021

Name: Rubaiya Kabir Pranti

VLANs and 802.1Q Trunks Inter-VLAN-Routing



NP Course NP Chapter 8

SRWE Modules 1 - 4:

Switching Concepts, VLANs, and InterVLAN Routing Exam

Upload

Record your answers in this PDF File SRWE-Lab1-Homework.pdf.

Write your answers in **red color**. You may use the comment capabilities of the free Adobe reader.

Upload the PDF file with your answers is Ilias.

NP	Networks and Protocols (NP)	Prof. Dr. A. Grebe
CCNA SRWE	Switching, Routing, and Wireless Essentials (SRWE)	

Homework / Preparation

Part 1: Cisco IOS Basic Configuration Commands

- a. Read the Lab Instructions of this Lab, and read NP chapters 8
- b. Check the **IOS Command List**, provided for the Labs and Review already used and new configuration commands.

Part 2: Recall Basic Configuration Commands

- a. Basic router interface commands
 - Configure router interface g0/1 with description "Link to LAN-A", IP address 172.16.10.1/29
 and activate it

R1(config)# interface g0/1
R1(config-if)# description Link to LAN-A
R1(config-if)# ip address 172.16.0.1 255.255.258
R1(config-if)# no shutdown

- Display the status of all interfaces in brief.
 R1# show ip interface brief or sh ip int br
- Display the detailed status of the interface g0/1

R1# show ip interface g0/1

- Display the routing table.

R1# show ip route

- Display the running configuration.

R1# show running-config or sh run

Part 3: Cisco IOS Switch VLAN / Trunk Commands

- a) Basic VLAN switch configurations
- Create VLAN 57 with name "students" on switch S1

S1(config)# vlan 57 S1(config-vlan)# name students NP Networks and Protocols (NP) Prof. Dr. A. Grebe
CCNA SRWE Switching, Routing, and Wireless Essentials (SRWE)

Configure S1 switch port f0/23 to be access port for VLAN 57

S1(config)# interface f0/23 S1(config-if)# switchport mode access S1(config-if)# switchport access vlan 57

- Display the VLAN database in brief

S1# show vlan brief

b) Basic Trunk switch configurations

- Configure the interface f0/5 as trunk port with native VLAN 99, VLAN allowed 57, 58, 59, 99

S1(config)# interface f0/5
S1(config-if)# switchport mode trunk
S1(config-if)# switchport trunk native vlan 99
S1(config-if)# switchport trunk allowed vlan 57,58,59,99

- Display the status of trunk interface f0/5

S1# show interface trunk f0/5

c) Basic SVI switch configurations

- Create management VLAN 100 (Name Management)

S1(config)# vlan 100 S1(config-vlan)# name Management

- Create the interface, configure IP address 192.168.100.11/24 for the management VLAN 100

S1(config)# interface vlan 100 S1(config-if)# ip address 192.168.100.11 255.255.255.0 S1(config-if)# no shutdown

- Set switch port f0/1 to be access port for VLAN 100.

S1(config)# interface f0/1
S1(config-if)# switchport mode access
S1(config-if)# switchport access vlan 100

Configure an IP default gateway with IP address 192.168.100.1 on switch S1.

S1(config)# ip default-gateway 192.168.100.1

NP	Networks and Protocols (NP)	Prof. Dr. A. Grebe
CCNA SRWE	Switching, Routing, and Wireless Essentials (SRWE)	

Part 4: Cisco IOS Inter-VLAN-Routing Commands

a) Switch Trunk to Router configurations

Configure the interface f0/5 of switch S1 as trunk port with native VLAN 100, VLAN allowed 10,20,100

S1(config)# interface f0/5
S1(config-if)# switchport mode trunk
S1(config-if)# switchport trunk native vlan 100
S1(config-if)# switchport trunk allowed vlan 10,20,100
S1(config-if)# exit

b) Router sub-interface and physical interface

- Create a sub-interface for VLAN 10 at router R1 interface g0/0 with description "VLAN 10 interface", IEEE 802.1q encapsulation and IP address 10.0.0.1 / 24.

```
R1(config)# interface g0/0.10
R1(config-subif)# description VLAN 10 interface
R1(config-subif)# encapsulation dot1Q 10
R1(config-subif)# ip address 10.0.0.1 255.255.255.0
further-
R1(config-subif)# exit
R1(config-if)# no shutdown (switching-on)
```

- Configure router R1 interface g0/0 as native trunk interface for VLAN 100 with description "VLAN 100 interface", IP address 192.168.100.1 / 24 and switch-on this physical interface.

```
R1(config)# interface g0/0.100
R1(config-if)# description VLAN 100 interface
R1(config-if)# ip address 192.168.100.1 255.255.255.0
R1(config-if)# exit
```