# T.I.P.I.D

## User Manual

Tracking Income, Purchases, and Individual Daily expenses

Maglanque, Ryza S. | Martin, Brenan T. | Sagum, Patrick Anthony M.

BSIT 2AG2 | IT 203 (Object-Oriented Programming)

# 1. Introduction

T.I.P.I.D is a desktop budget tracker built with Java Swing. It helps a user plan a monthly budget, split it into spending categories, record expenses, and review where the money went. An administrator can monitor registered accounts, unblock locked accounts, and delete accounts.

This manual covers both roles: the **User** (budget owner) and the **Admin** (account manager).

**Important:** all data is kept in memory only. Accounts, budgets, and transactions you create are lost when the program is closed. Only the built-in sample data returns on the next launch.

# 2. Getting Started

## 2.1 Requirements

- Java JDK installed
- Apache NetBeans IDE (the project uses Apache Ant)
- The `Image` folder placed inside `src`, so logos and icons load

## 2.2 Running the program

1. Open the project in NetBeans (File > Open Project).
2. Right-click `LogInForm.java` and choose **Run File** (or press Shift + F6).
3. The Log-in screen opens maximized.

## 2.3 Default accounts for testing

- **User:** username `Tipida`, password `pass`. This account comes with sample budgets and transactions for May 2025, September 2026, and October 2026.
- **Admin:** username `Admin`, password `password`. After the password, the system asks for the security hint: `Hello World!`

# 3. Creating an Account and Logging In

## 3.1 Create an account

1. On the Log-in screen, click **Create an account**.
2. Enter a **Username**, a **Password**, and the same password again under **Confirm Password**.
3. Click **Register**, then click **Yes** to confirm.
4. A success message appears and you are returned to the Log-in screen.

You will see an error if a field is empty, if the username is already taken, or if the two passwords do not match. Click **Cancel** to go back without registering.





Figure 1. Create account screen.

## 3.2 Log in as a user

1 Enter your username and password. Tick **Show Password** to see what you typed.

2 Click **Log-in**. You land on the Dashboard.

If your account has saved budget months, the most recently saved one becomes the active period automatically.





Figure 2. Log-in screen.

## 3.3 Account lockout

After **3 wrong passwords** in a row, the account is blocked. The message shows how many attempts remain before that happens. A blocked account cannot log in until the administrator unblocks it (hotline shown on screen: 041-125). A correct log-in resets the failed-attempt counter.

## 3.4 Log in as admin

1 Enter `Admin` and the admin password.

2 In the **Admin Verification** box, type the security hint and click OK.

3 A wrong hint is rejected and you stay on the Log-in screen.

# 4. Common Features (User and Admin)

## 4.1 The header menu

The blue header shows the T.I.P.I.D logo and title. Click the **dashboard icon** at the top-right corner to open or close the dropdown menu:

- **Hi, (your username)!** greeting
- **Change Password**
- **Log-out**





Figure 3. The header dropdown menu (Change Password and Log-out), shown on the user Dashboard.

## 4.2 Change your password

1 Open the dropdown and click **Change Password**.

2 Enter your current password, the new password, and the new password again.

3 Click OK.

The change is rejected if any field is empty, the current password is wrong, or the two new passwords do not match.

## 4.3 Log out

Choose **Log-out** in the dropdown and confirm with Yes. You return to the Log-in screen.

# 5. User Guide

After logging in, four tabs appear below the header: **Dashboard**, **Budget**, **Transactions**, and **Spending History**. Click a tab to open it. The tab you are on is shown in bold blue. Amounts are shown with a **P** (Philippine peso).

## 5.1 Recommended first-time workflow

1. Go to **Budget** and set a total budget and category budgets for a month.
2. Go to **Transactions** and record your expenses.
3. Check the **Dashboard** to see progress.
4. Use **Spending History** to search and sort everything you have recorded.

## 5.2 Budget page

This is where you set the monthly budget. A transaction cannot be added until a monthly budget exists.

**Page elements**

- **Active For:** a list of your saved months. Choosing one makes it the active period for the Dashboard and Transactions pages.
- **Total Budget** and **Allocated Budget:** the total you entered, and the sum of all category budgets. Allocated turns red if it is more than the total.
- **Select Month**, **Enter Year**, **Enter Total Budget**
- One box per category, each showing **Spent** and **Left** for the month.

**Categories:** Food & Dining, Bills & Utilities, Debt Payments, Savings, Transport, Health, Entertainment, Other.

**To set or change a budget**

1. Click **Edit** to unlock the fields.
2. Pick the **month**, type the **year**, and type the **total budget**. The category boxes unlock only after the year and total are filled in.
3. Type an amount for each category you plan to use. Blank boxes count as 0. Commas are allowed.
4. Click **Set** to save. You will see "Budget settings saved successfully!"

While you type, Allocated, Spent, and Left update live. A month that is typed but not yet saved appears in Active For marked "(draft)".

**Budget rules. Nothing is saved unless all of these hold:**

- Year is between 1900 and 9999.
- The month is not in the future.
- No amount is negative or non-numeric.

- Each category budget is at least the amount already spent in that category.
- The total budget is at least the sum of the category budgets.

To edit an older month, choose it in Active For, click Edit, and change it.





Figure 4. Budget page.

## 5.3 Transactions page

This page records expenses for the **active period** (shown at the top of the form). If no period is set, you are asked to set a monthly budget first.





Figure 5. Transactions page: the table of records and the Add a transaction form.

### Form fields

- **Category:** pick one ("-- Select Category --" is not valid). Below it, the Budget and Left amounts of the chosen category are displayed.
- **Item Number:** generated automatically (format TN plus a number) and read-only.
- **Description:** what you bought.

- **Amount:** must be greater than zero.
- **Day (1-31):** the day of the active month. The full date is built from the active month and year.

**Buttons**

- **New:** unlocks the form and generates a new item number. The form stays locked until you click New.
- **Add:** saves a new transaction after you confirm.
- **Update:** changes the selected transaction after you confirm.
- **Delete:** removes the selected transaction after you confirm.
- **Clear:** empties the form and locks it again.

**To add a transaction**

1. Click **New**.
2. Choose a category and fill in description, amount, and day.
3. Click **Add** and confirm.

**To update or delete a transaction**

1. Click a row in the table (columns: Transaction Number, Description, Category, Amount, Date). Its details fill the form.
2. Edit the fields and click **Update**, or click **Delete**. Confirm the prompt.

**Validation you may run into**

- "Please select a valid category!"
- "Set a monthly budget first."
- "Complete all the transaction details!"
- "Amount must be greater than zero."
- "That day does not exist" for the month (for example day 31 in a 30-day month).
- "You cannot add a transaction for a future date!"
- **Budget Exceeded:** the expense is larger than what is left in that category. The message shows the remaining amount. Either lower the amount or raise that category's budget on the Budget page. When updating, the transaction being edited is not counted twice.

## 5.4 Dashboard

A read-only overview of the active period:





Figure 6. Dashboard.

- **Total Budget, Total Spent, Remaining, Budgeted** cards at the top. Budgeted is the amount allocated across categories.
- **Spending Breakdown:** a pie chart with each category's percentage of your spending. The chart is gray when nothing has been spent.
- **Category Progress:** a bar per category showing amount spent against its budget.
- **Active Period panel:** your transactions for the month, newest first. Click **View All** to jump to the Transactions page.

## 5.5 Spending History

This page covers **all months** of your account in one table. It has:

- **Search:** results update as you type. It matches description, transaction number, date, category, or amount. Press Enter on a search with no matches to see "Search not found."
- **Sort and filter dropdown:** All Transactions, Oldest to Latest, Latest to Oldest, Lowest to Highest Spent, Highest to Lowest Spent, or Filter by Category. Choosing Filter by Category reveals a category dropdown.

Search and the sort/filter choice work together.





Figure 7. Spending History page.

# 6. Admin Guide

The Admin screen is titled **Admin Overview - User monitoring**.





Figure 8. Admin Overview with the User Accounts table and the Unblock User and Delete User buttons.

- **Total Users:** the number of registered user accounts (the Admin account is not counted).
- **User Accounts table:** columns are User ID, User Name, and Status (Active or Blocked). A counter beneath shows how many accounts are currently displayed.
- **Search box:** live search by username or user ID.
- **Status filter:** All, Active, or Blocked.

## 6.1 Unblock a user

1 Select the account in the table.

2 Click **Unblock User**.

3 A success message appears and the status returns to Active.

If the selected account is not blocked, the system says so. Choosing no account shows "Please select an account first."

### 6.2 Delete a user

1 Select the account in the table and click **Delete User**.

2 Confirm "Do you want to delete this account?"

3 Enter the **admin password** when asked.

4 The account and all of its budgets and transactions are removed.

This cannot be undone. A wrong admin password cancels the deletion.

### 6.3 Change the admin password

Use the dropdown menu in the header, the same way a user does (section 4.2).





Figure 9. The admin header dropdown menu.

## 7. Troubleshooting

- **Logos or icons are missing, or the program fails to start:** make sure the `Image` folder is inside `src`.
- **My account is blocked:** ask the administrator to unblock it.
- **My data disappeared:** the system stores data in memory only, so closing the program clears it.
- **I cannot add a transaction:** set a budget for the month first, then click New on the Transactions page.
- **Budget will not save:** check that no category budget is below what is already spent, the total covers all category budgets, and the month is not in the future.

- **Expense rejected as exceeding the budget:** raise that category's budget on the Budget page, or lower the amount.

## 8. Quick Reference

- **Login lockout:** 3 failed attempts
- **Item number format:** TN followed by a number
- **Date format shown:** for example, October 18, 2026
- **Categories (8):** Food & Dining, Bills & Utilities, Debt Payments, Savings, Transport, Health, Entertainment, Other
- **Future months and dates:** not allowed
- **Storage:** memory only, resets when the program closes