


PrimedGun Setup Guide

1. Add Dolphin To Steam

Add Dolphin to Steam as a non-Steam game, then set Throttling Behavior to Fixed, lock application framerate to 60 FPS, and use about 16.67 ms additional prediction.



PrimedGun Setup Guide

2. Dolphin VR Hotkey

For Reset VR Position, right-click the button selection, clear it, then add new input. Assign it to a controller button so recentering is easy in-game.

Hotkey Settings

Device

OpenXR/0/OpenXR Controller

Refresh

Reset

Default

Clear

Profile

Load

Save

General

TAS Tools

Debugging

Wii and Wii Remote

Controller Profile

Graphics

VR

USB Emulation

3D

Save and Load State

Other

VR

Toggle OpenXR

Reset VR Position

Right Button Thumbstick

Decrease Units Per Meter

Increase Units Per Meter

Decrease Lean Back Angle

Increase Lean Back Angle

Decrease Camera Forward

Increase Camera Forward

Toggle Virtual Screen

Decrease Screen Distance

Increase Screen Distance

Decrease Screen Size

Increase Screen Size

Decrease Screen Curvature

Increase Screen Curvature

Toggle Don't Clear Screen

Toggle Force VBI

Toggle Remove Cinematic Bars

Shader

Toggle Shader Hunting

Cycle Hunting Option

Cycle Shader Type

Cycle Override Handling

Previous Shader

Next Shader

Previous Texture Hash

Next Texture Hash

Toggle Texture Hash Filter


Save Shader Override

Close

PrimedGun Setup Guide

3. Dolphin Controller Mapping


Right-click the button selection, clear it, then add new input. The D-pad does not need manual input bindings: PrimedGun reads the control stick as visor D-pad input when the controller is near your head. Additionally, offhand controller yaw is used for directional strafing.



PrimedGun Setup Guide

4. Metroid Prime World Scale

In Metroid Prime properties, adjust World Scale to 1.50 as shown.



PrimedGun Setup Guide

5. Dolphin AR Codes

Apply all PrimedGun AR codes in Dolphin before playing.

You can copy the full AR code list from README.md in the PrimedGun folder or from the GitHub page.

Use the codes with Metroid Prime GCN NTSC Rev 0 (GM8E01).

PrimedGun Setup Guide

Usage And Notes

Usage

1. Start SteamVR.
2. Start Dolphin and load Metroid Prime.
3. Launch PrimedGun.exe.
4. Confirm both Dolphin and OpenVR show as connected.
5. Click INACTIVE to start writing transforms.
6. While moving your head, use Dolphin's reset-view toggle to line the arm cannon up with your controller position.
It's best to assign the reset-view toggle to your controller for this.
7. If playing seated or standing, adjust the Y axis in Offset Tuning as needed.

Recommended Dolphin Version

Use DolphinXR from:

<https://github.com/iChris4/dolphinXR/releases>

Notes

- Settings are saved to primedgun_settings.ini.
- The app reads controller tracking from OpenVR and writes the cannon transform into Dolphin memory.
- The project is OpenVR-only. Old OpenXR experiments have been removed.
- For the best experience, try not to turn your body around. You can move in the game like this, but functionality is not ideal.

For further enhancements to your VR experience, join the Dolphin VR Discord.

Thank you to the Metroid Prime modding community for the resources and research that helped make this possible.