


Aim: Create simple Adhoc network.



Download the INET sources.

- Unpack it into the directory of your choice: (tar xvfz inet-<version>.tgz)(recommended is tar or .tgz)
- Recommended version is inet 2.1
- Start the Omnet++ IDE, and import the project via File -> Import -> Existing Projects to the

```

Welcome to OMNet++ 4.2.2!

Type "./configure" and "make" to build the simulation libraries.

When done, type "omnetpp" to start the IDE.

ADMIN@DESKTOP-NIQAMS3 ~
$ user@computer ~/omnetpp-4.2.2
sh: user@computer: command not found

ADMIN@DESKTOP-NIQAMS3 ~
$ cd /c/Users/ADMIN/Downloads/omnetpp-4.2.2-src-windows/omnetpp-4.2.2

ADMIN@DESKTOP-NIQAMS3 ~
$ ./configure
checking build system type... i686-pc-mingw32
checking host system type... i686-pc-mingw32
configure: -----
configure: reading configure.user for your custom settings
configure: -----
checking for icc... no
checking for gcc... gcc
checking for C compiler default output file name... a.exe
checking whether the C compiler works... yes
checking whether we are cross compiling... no
checking for suffix of executables... .exe
checking for suffix of object files... o
checking whether we are using the GNU C compiler... yes
checking whether gcc accepts -g... yes
checking for gcc option to accept ISO C89... none needed
checking for lpc... no
checking for g++... g++
checking whether we are using the GNU C++ compiler... yes
checking whether g++ accepts -g... yes
checking for g++... g++
checking for ranlib... ranlib
checking whether g++ supports -fno-stack-protection... yes
checking whether g++ supports -Wl,-no-as-needed... yes
checking whether g++ supports -Wl,-as-needed... yes
checking for swapcontext... no
checking if shared libs need -fpic... no

ADMIN@DESKTOP-NIQAMS3 ~
$ make
make[1]: Entering directory '/c/Users/ADMIN/Downloads/omnetpp-4.2.2-src-windows/omnetpp-4.2.2'
make[1]: *** No rule to make target 'all'.  Stop.
make: *** [Makefile:10: all] Error 2

ADMIN@DESKTOP-NIQAMS3 ~
$ make clean
make[1]: Entering directory '/c/Users/ADMIN/Downloads/omnetpp-4.2.2-src-windows/omnetpp-4.2.2'
make[1]: *** No rule to make target 'clean'.  Stop.
make: *** [Makefile:10: clean] Error 2


ADMIN@DESKTOP-NIQAMS3 ~
$ make install
make[1]: Entering directory '/c/Users/ADMIN/Downloads/omnetpp-4.2.2-src-windows/omnetpp-4.2.2'
make[1]: *** No rule to make target 'install'.  Stop.
make: *** [Makefile:10: install] Error 2

```


Aim: Create simple Adhoc network.

Steps for practical:


- Then open inet/examples/
- Right click on adhoc -create new folder as SimpleAdhoc.
- Right click on your newly created folder and select NED file. Give name as Net1.




Aim: Create simple Adhoc network.



Aim: Create simple Adhoc network.




click on new manages mobility wireless network wizard.




then configure as follows

Aim: Create simple Adhoc network.



then click on finish.



below is the code that will be available in source part of net1.ned once configured.

Aim: Create simple Adhoc network.

The screenshot displays the OMNeT++ IDE interface for editing the `Net1.ned` file. The main editor shows the following configuration:

```
[General]
network = Net1

*.numOfHosts = 5

#debug-on-errors = true
tkenv-plugin-path = ../../etc/plugins

**.mobility.constraintAreaMinZ = 0m
**.mobility.constraintAreaMaxZ = 0m
**.mobility.constraintAreaMinX = 0m
**.mobility.constraintAreaMinY = 0m
**.mobility.constraintAreaMaxX = 600m
**.mobility.constraintAreaMaxY = 400m

i **.debug = false
i **.coreDebug = false

i **.channelNumber = 0

# channel physical parameters
*.channelControl.carrierFrequency = 2.4GHz
*.channelControl.pMax = 20.0mW
*.channelControl.sat = -110dBm
i *.channelControl.alpha = 2

# mobility
**.host[*].mobilityType = "MassMobility"
**.host[*].mobility.changeInterval = truncnormal(2s, 0.5s)
**.host[*].mobility.changeAngleRv = normal(0deg, 30deg)
```

Below the editor, the 'Problems' and 'NED Parameters' panels are visible. The 'NED Parameters' panel shows a table of parameters for the 'Net1' network:

Parameter	Value	Remark
Net1.numOfHosts	5	ini: see [General] / *.numOfHosts=5
Net1.host[*].numExtInterfaces	0	NED default applied implicitly
Net1.host[*].numRadios	1	NED default applied implicitly
Net1.host[*].numCapRecorders	0	NED default applied implicitly
Net1.host[*].mobilityType	"MassMobility"	ini (overrides NED default: numRadios > ...)
Net1.host[*].routingFile	""	NED default applied implicitly

The 'Project Explorer' on the left shows the project structure, including the `examples/adhoc/SimpleAdhoc` directory where `Net1.ned` is located. A context menu is open over the `Net1.ned` file, showing options like 'Run', 'Debug', 'Run History', 'Run As', 'Run Configurations...', 'Debug History', 'Debug As', 'Debug Configurations...', and 'External Tools'. The 'Run' option is highlighted, and a tooltip indicates '1 OMNeT++ Simulation'.

Aim: Create simple Adhoc network.

The screenshot displays the OMNeT++ IDE interface for a simulation. The main window shows a network diagram with a central access point (ap) and four hosts (host[0], host[1], host[2], host[3]) connected to it. The network is titled 'Net1' and is part of a simulation named 'inet.examples.adhoc.SimpleAdhoc.Net1'. The console window on the right shows the simulation's progress, including the loading of NED files and the initialization of modules. The status bar at the bottom indicates the system temperature is 29°C and the date is 26-08-2026.

Net1 (Net1) (id=1)

channelConfigurator host[0] host[3] host[2] host[4] ap host[1]

Zoom: 0.65x

Simulation - inet/examples/adhoc/SimpleAdhoc/omnetpp.ini - OMNeT++ IDE

File Edit Source Navigate Search Project Run Window Help

Net1.ned omnetpp.ini

```
[General]
network = Net1
*.numOfHosts = 5
4
```

Form Source

Problems Module Hierarchy NED Parameters NED Inheritance Console

Net1 [OMNeT++ Simulation] C:\Users\ADMIN\Downloads\omnetpp-4.2.2-src-windows\omnetpp-4.2.2\bin\opp_run.exe (26/8/26 1:11 AM - run)

LOADING NED FILES FROM ... 126

Loading NED files from .../src: 248

Loading images from C:\Users\ADMIN\Downloads\omnetpp-4.2.2-src-windows\omnetpp-4.2.2\images:

Plugin path: C:\Users\ADMIN\Downloads\inet-2.1.0\inet-2.1.0\etc\plugins; ./plugins

Loading tcl files from C:\Users\ADMIN\Downloads\inet-2.1.0\inet-2.1.0\etc\plugins: contextme

OMNeT++/Tkwin - Net1

File Edit Simulate Trace Inspect View Options Help

Run #0: Net1 Event #1 T=0.007103605871 Next: Net1.ap.wlan[0].mgmt (id=88)

Msgs scheduled: 11 Msgs created: 64 Msgs present: 64

Ev/sec: n/a Simsec/sec: n/a Ev/simsec: n/a

beaconTimer move... move... startUp startUp

Net1 (Net1) (id=1)

scheduled-events

- Initializing module Net1.host[3].wlan[0].radio, stage 2
- Initializing AbstractRadio, stage=2
- Initializing module Net1.host[4].mobility, stage 2
- Initializing MobilityBase stage 2
- Initializing MovingMobilityBase stage 2
- Initializing LineSegmentsMobilityBase stage 2
- Initializing MassMobility stage 2
- Initializing module Net1.host[4].networkLayer.ar, stage 2
- Initializing module Net1.host[4].routingTable, stage 2
- Initializing module Net1.host[4].wlan[0].radio, stage 2
- Initializing AbstractRadio, stage=2
- Initializing module Net1.ap.wlan[0].radio, stage 2
- Initializing AbstractRadio, stage=2
- Initializing module Net1.configurator, stage 2

29°C Partly cloudy Search ENG IN 02:00 26-08-2026