Load Balancer

Create Security Group





Create Instance







Run each instance Public IP

This is a load balancer ip-172-31-34-45.eu-north-1.compute.internal

This is a load balancer ip-172-31-41-97.eu-north-1.compute.internal

This is a load balancer ip-172-31-41-221.eu-north-1.compute.internal

Create Load balancer





Select All Availability Zone




EC2 > Load balancers > Create Classic Load Balancer
Attributes
Creating your load balancer using the console gives you the opportunity specify additional features at launch. You can also find and adjust these settings in the load balancer's "Attributes" section after your load balancer is created.
Enable cross-zone load balancing
With cross-zone load balancing, each load balancer node for your Classic Load Balancer distributes requests evenly across the registered instances in all enabled Availability Zones. If cross-zone load balancing is disabled, each load balancer node distributes requests evenly across the registered instances in its Availability Zone only. Classic Load Balancers created with the API or CLI have cross-zone load balancing disabled by default. After you create a Classic Load Balancer, you can enable or disable cross-zone load balancing at any time.
Enable connection draining
Applicable to instances that are deregistering, this feature allows existing connections to complete (during a specified draining interval) before reporting the instance as deregistered. Learn more
Timeout (draining interval)
The maximum time for the load balancer to allow existing connections to complete. When the maximum time limit is reached, the load balancer forcibly closes any remaining connections and reports the instance as deregistered.
5
seconds
Valid values: 1-3600 (integers only)
Load balancer tags - optional
Consider adding tags to your load balancer. Tags enable you to categorize your AWS resources so you can more easily manage them. The 'Key' is required, but 'Value' is optional.


aws
Search
[Alt+S]
United States (N. Virginia)
Sakshi Jain
EC2 > Load balancers
Network & Security
Security Groups
Elastic IPs
Placement Groups
Key Pairs
Network Interfaces
Load Balancing
Load Balancers
Load balancers (1)
What's new?
Actions
Create load balancer
Elastic Load Balancing scales your load balancer capacity automatically in response to changes in incoming traffic.
Filter load balancers
1
Name
State
Type
Scheme
IP address type
VPC ID
Load-balancer
–
classic
-
-
vpc-041fc