Elastic File System

EFS (Elastic File System) is a **shared storage service** in AWS that can be **mounted on multiple EC2 instances at the same time**.

1. Create EFS
   Click on Customize



This feature helps you **save money** by automatically moving files to cheaper storage classes based on how frequently they are accessed.
EFS has 3 storage classes:

- **Standard** — Default & most expensive
- **Infrequent Access (IA)** — Cheaper storage
- **Archive** — Very cheap, for long-term 'cold' data

Lifecycle rules automatically move data between these classes.





A mount target provides an NFSv4 endpoint at which you can mount an Amazon EFS file system. We recommend creating one mount target per Availability Zone.





2. Goto security Group of EFS



Edit Inbound Rule



3. Create EC2 Instance



4. Click on Attach

Copy IP Address



5. Connect with EC2 Instance

```
   ,     #_
   ~\_  ####_        Amazon Linux 2023
  ~~  \_#####\
  ~~     \###|
  ~~       \#/ ___   https://aws.amazon.com/linux/amazon-linux-2023
   ~~       V~' '->
    ~~~         /
      ~~._.   _/
         _/ _/
       _/m/'
Last login: Fri Dec 12 16:44:05 2025 from 13.48.4.202
[ec2-user@ip-172-31-23-7 ~]$ sudo -i
[root@ip-172-31-23-7 ~]# df -hT
Filesystem        Type      Size  Used Avail Use% Mounted on
devtmpfs          devtmpfs  4.0M     0  4.0M   0% /dev
tmpfs             tmpfs     459M     0  459M   0% /dev/shm
tmpfs             tmpfs     184M  436K  183M   1% /run
/dev/nvme0n1p1    xfs       8.0G  1.6G  6.4G  20% /
tmpfs             tmpfs     459M     0  459M   0% /tmp
/dev/nvme0n1p128  vfat       10M  1.3M  8.7M  13% /boot/efi
tmpfs             tmpfs      92M     0   92M   0% /run/user/1000
[root@ip-172-31-23-7 ~]# vim /etc/fstab
```

```
#
UUID=170fd7a4-f127-46eb-a3be-8b380dc8d94a     /           xfs    defaults,noatime  1   1
UUID=7BBE-6739        /boot/efi       vfat    defaults,noatime,uid=0,gid=0,umask=0077,shortname=winnt,x-systemd.automount 0 2
172.31.23.176:/ /mnt     nfs4     default         0        0
~
~
~
~
```

```
[root@ip-172-31-23-7 ~]# mount -a
[root@ip-172-31-23-7 ~]# df -hT
Filesystem        Type      Size  Used Avail Use% Mounted on
devtmpfs          devtmpfs  4.0M     0  4.0M   0% /dev
tmpfs             tmpfs     459M     0  459M   0% /dev/shm
tmpfs             tmpfs     184M  432K  183M   1% /run
/dev/nvme0n1p1    xfs       8.0G  1.6G  6.4G  20% /
tmpfs             tmpfs     459M     0  459M   0% /tmp
/dev/nvme0n1p128  vfat       10M  1.3M  8.7M  13% /boot/efi
tmpfs             tmpfs      92M     0   92M   0% /run/user/1000
172.31.23.176:/   nfs4      8.0E     0  8.0E   0% /mnt
[root@ip-172-31-23-7 ~]#
```