


Номер варианта 7

Основание системы счисления	X ₁	X ₂	X ₃	X ₄	X ₅
10	435	317	13	3815	15
16	1B3	13D	D	EE7	F


Выполнить пошаговое вычисление выражения: $Y = [(X_1 + X_2) * X_3 - X_4] / X_5$

Действие	Операнд 1	Операнд 2	Результат
Сложение	435 (1B3)	317 (13D)	752 (2F0)
Умножение	752 (2F0)	13 (D)	9776 (2630)
Вычитание	9776 (2630)	3815 (EE7)	5961 (1749)
Деление	5961 (1749)	15 (F)	397 остаток 4 (18D остаток 6)


Сложение



Умножение



Вычитание




The screenshot shows a Windows XP desktop with a desktop background of a green field and blue sky. A debugger window titled "C:\WINDOWS\system32\cmd.exe - debug" is open. The assembly code displayed is as follows:

```
AX=2630 BX=0000 CX=0000 DX=0000 SP=FFEE BP=0000 SI=0000 DI=0000
DS=0B0D ES=0B0D SS=0B0D CS=0B0D IP=0102 NU UP EI PL NZ NA PE NC
0B0D:0102 1E      PUSH    DS
--r ip
IP 0102
--e 100
0B0D:0100 F7.29    E3.d8
--r ip
IP 0102
--e 100
--r bx
BX 0000
--ee?
--r
AX=2630 BX=0EE7 CX=0000 DX=0000 SP=FFEE BP=0000 SI=0000 DI=0000
DS=0B0D ES=0B0D SS=0B0D CS=0B0D IP=0100 NU UP EI PL NZ NA PE NC
0B0D:0100 29D8    SUB     AX,BX
--t
AX=1749 BX=0EE7 CX=0000 DX=0000 SP=FFEE BP=0000 SI=0000 DI=0000
DS=0B0D ES=0B0D SS=0B0D CS=0B0D IP=0102 NU UP EI PL NZ AC PO NC
0B0D:0102 1E      PUSH    DS
--r ip
IP 0102
--e 100
0B0D:0100 F7.29    E3.d8
```

The taskbar at the bottom shows the "Пуск" (Start) button, the taskbar title "C:\WINDOWS\system...", and the system clock "4:15".

Деление



The screenshot shows a Windows XP desktop with a desktop background of a green field and blue sky. A debugger window titled "C:\WINDOWS\system32\cmd.exe - debug" is open. The assembly code displayed is as follows:

```
DS=0B0D ES=0B0D SS=0B0D CS=0B0D IP=0100 NU UP EI PL NZ NA PE NC
0B0D:0100 29D8    SUB     AX,BX
--t
AX=1749 BX=0EE7 CX=0000 DX=0000 SP=FFEE BP=0000 SI=0000 DI=0000
DS=0B0D ES=0B0D SS=0B0D CS=0B0D IP=0102 NU UP EI PL NZ AC PO NC
0B0D:0102 1E      PUSH    DS
--r ip
IP 0102
--e 100
0B0D:0100 29.F7    D8.f3
--r ip
IP 0102
--e 100
--r bx
BX 0EE7
--f
--r
AX=1749 BX=000F CX=0000 DX=0000 SP=FFEE BP=0000 SI=0000 DI=0000
DS=0B0D ES=0B0D SS=0B0D CS=0B0D IP=0100 NU UP EI PL NZ AC PO NC
0B0D:0100 F7F3    DIV     BX
--t
AX=018D BX=000F CX=0000 DX=0006 SP=FFEE BP=0000 SI=0000 DI=0000
DS=0B0D ES=0B0D SS=0B0D CS=0B0D IP=0102 NU UP EI PL NZ AC PO NC
0B0D:0102 1E      PUSH    DS
```

The taskbar at the bottom shows the "Пуск" (Start) button, the taskbar title "C:\WINDOWS\system...", and the system clock "4:16".

Все вычисления точные