MAINNET ADDRESSES

1. **InitHash**   :
0x5c7eea802f4588d3d0d84fa61a93156f9fbaeef4c4d0255c8a786f29bd0ec7bf

2. **FAST**   : 0xC888A0Ab4831A29e6cA432BaBf52E353D23Db3c2
3. **FASTBAR**   : 0x70424E8d4311B1305Dc0751FE6ea0cAf1e2a60EA
4. **FACTORY**   : **0x5bDdC63f23c0386fb817959773c32b736744c899**
5. **WETH**   : 0xC02aaA39b223FE8D0A0e5C4F27eAD9083C756Cc2
6. **FASTMAKER** : 0xf3CaA3b9E55eF1908fbb00556e2E11B4158F324b
7. **ROUTER**   : **0x248c828698Cfb736a9eb9e72F7ad4175fEB4dEAb**

DEPLOYMENT STEPS
----

1. **Factory Contract**   **[Factory.sol]**

   a. Compiler Configurations

   - i.   Compiler Version   : **v0.6.12**+commit.27d51765
   - ii.   EVM Version   : default evmVersion
   - iii. Optimization Enabled   : Yes with **200** runs

   b. Deploy Settings
   - i.   **Parameter** [FeeSetter = deployer address]
   - ii.   Now deploy Factory Contract
   - iii. Note down its **code init hash**.

----

2. **FastMaker Contract**   **[FastMaker.sol]**

   a. Compiler Configurations

   - i.   Compiler Version   : **v0.6.12**+commit.27d51765
   - ii.   EVM Version   : default evmVersion
   - iii. Optimization Enabled   : Yes with **5000** runs

   b. Parameters
   - i.   _factory: <>
   - ii.   _bar: <>
   - iii. _sushi: <>
   - iv.   _weth: <>

   c. Now deploy FastMaker contract

   - a. Go to Factory contract and set
   - b. FeeTo = FastMakerAddress

----

3. **Router Contract**   **[FastSushiRouter.sol]**

   a. Changes in contract

      i.   Replace with new code init hash got from factory contract.

   b. Compiler Configurations

      i.   Compiler Version   : **v0.6.12**+commit.27d51765
      ii. EVM Version   : default evmVersion
      iii. Optimization Enabled : Yes with **200** runs

----

4. **FastBar[xFAST] Contract**   **[FastBar.sol]**

   a. Compiler Configurations

      i.   Compiler Version   : **v0.6.12**+commit.27d51765
      ii. EVM Version   : default evmVersion
      iii. Optimization Enabled : Yes with **200** runs

   b. Deploy Settings

      i.   Set **Parameters [address FAST].**
      ii. Deploy The contract

Code Init :
0x44286c1e9aae066f27c898b6054ed05a1e5f244503a94f4c74006910dcbba61a

Fast   : 0x5de6CF4913A1636fa3f7ac3862C6fD91Bf558Bb6
FastBar : 0xB7D28616848735d0653F4A7A0708fb6E95c056eA

   Factory : 0x7Bd7ba8A91308373Cb084C61586F4C47609Dc428
FastMaker : 0x63E74B821Ab663E261dA4D7B5527825993a6cb88

   Router : 0xD6616512c56295B2c796cDe18cd531C9CECb48Cb
WETH   : 0xc778417E063141139Fce010982780140Aa0cD5Ab