Slider

````
---
title: Slider
description: An input where the user selects a value from within a given range.
base: base
component: true
links:
  doc: https://base-ui.com/react/components/slider
  api: https://base-ui.com/react/components/slider#api-reference
---

<ComponentPreview styleName="base-nova" name="slider-demo" />

## Installation

<CodeTabs>

<TabsList>
  <TabsTrigger value="cli">Command</TabsTrigger>
  <TabsTrigger value="manual">Manual</TabsTrigger>
</TabsList>
<TabsContent value="cli">

```bash
npx shadcn@latest add slider
```

</TabsContent>

<TabsContent value="manual">

<Steps className="mb-0 pt-2">

<Step>Install the following dependencies:</Step>

```bash
npm install @base-ui/react
```

<Step>Copy and paste the following code into your project.</Step>

<ComponentSource
  name="slider"
  title="components/ui/slider.tsx"
  styleName="base-nova"
/>

<Step>Update the import paths to match your project setup.</Step>

</Steps>

</TabsContent>

</CodeTabs>

## Usage

```tsx
import { Slider } from "@/components/ui/slider"
```
````

```tsx
<Slider defaultValue={[33]} max={100} step={1} />
```

Range

Use an array with two values for a range slider.

<ComponentPreview styleName="base-nova" name="slider-range" />

Multiple Thumbs

Use an array with multiple values for multiple thumbs.

<ComponentPreview styleName="base-nova" name="slider-multiple" />

Vertical

Use `orientation="vertical"` for a vertical slider.

<ComponentPreview styleName="base-nova" name="slider-vertical" />

Controlled

<ComponentPreview styleName="base-nova" name="slider-controlled" />

Disabled

Use the `disabled` prop to disable the slider.

<ComponentPreview styleName="base-nova" name="slider-disabled" />

RTL

To enable RTL support in shadcn/ui, see the [RTL configuration guide](/docs/rtl).

<ComponentPreview styleName="base-nova" name="slider-rtl" direction="rtl" />

API Reference

See the [Base UI Slider](https://base-ui.com/react/components/slider#api-reference) documentation.