TORCH.NORM

torch.norm(input, p='fro', dim=None, keepdim=False, out=None, dtype=None)

[SO RCE]

Returns the matrix norm or vector norm of a given tensor.

• WARNING

torch.norm is eprecate an may eremove in a future PyTorch release. se torch.linalg.norm() instea , ut note that torch.linalg.norm() has a ifferent signature an slightly ifferent ehavior that is more consistent with NumPy's numpy.linalg.norm.

Parameters

- in ut (Tensor) the input tensor
- (int, float, inf, -inf, 'fro', 'nuc', optional) -

the or er of norm. Default: 'fro' The following norms can e calculate :

or	matrix norm	vector norm
None	Fro enius norm	2-norm
'fro'	Fro enius norm	-
'nuc'	nuclear norm	-
Other	as vec norm when im is None	sum(a s(x)**or)**(1./or)

- **im** (*int*, 2-tuple of python:ints, 2-list of python:ints, optional) If it is an int, vector norm will e calculate, if it is 2-tuple of ints, matrix norm will e calculate. If the value is None, matrix norm will e calculate when the input tensor only has two imensions, vector norm will e calculate when the input tensor only has one imension. If the input tensor has more than two imensions, the vector norm will e applie to last imension.
- **kee im** (bool, optional) whether the output tensors have dim retaine or not. Ignore if dim = None an out = None . Default: False
- out (Tensor, optional) the output tensor. Ignore if dim = None an out = None.
- **ty e** (torch.dtype, optional) the esire ata type of returne tensor. If specifie, the input tensor is caste to :attr:' type' while performing the operation.

 Default: None.

Example:

```
>>> import torch
>>> a = torch.arange(9, dtype= torch.float) - 4
>>> b = a.reshape((3, 3))
>>> torch.norm(a)
tensor(7.7460)
>>> torch.norm(b)
tensor(7.7460)
>>> torch.norm(a, float('inf'))
tensor(4.)
>>> torch.norm(b, float('inf'))
tensor(4.)
>>> c = torch.tensor([[ 1, 2, 3],[-1, 1, 4]] , dtype= torch.float)
>>> torch.norm(c, dim=0)
tensor([1.4142, 2.2361, 5.0000])
>>> torch.norm(c, dim=1)
tensor([3.7417, 4.2426])
>>> torch.norm(c, p=1, dim=1)
tensor([6., 6.])
>>> d = torch.arange(8, dtype= torch.float).reshape(2,2,2)
>>> torch.norm(d, dim=(1,2))
tensor([ 3.7417, 11.2250])
>>> torch.norm(d[0, :, :]), torch.norm(d[1, :, :])
(tensor(3.7417), tensor(11.2250))
```

✓ Previous

© Co yright 2019, Torch Contri utors.

Built with S hinx using a theme rovi e y Rea the Docs.

Access com rehensive evelo er ocumentation for PyTorch View Docs

Get in- e th tutorials for eginners an a vance evelo ers

Email A ress

View Tutorials

Fin evelo ment resources an get your uestions answere View Resources

PyTorch Resources Stay Connecte

Get Starte Tutorials

Features Docs Ecosystem Discuss

Blog Githu Issues

Contri uting Bran Gui elines