
Практическая №29

Строим схему и все настраиваем.



У устройства Home VoIP прописываем адрес сервера.

Global Settings
Home VoIP0
10.3.0.1

Конфигурируем Router0.

```
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config) #interface fa0/0
Router(config-if) # ip address 10.3.0.1 255.255.255.0
Router(config-if) #no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
Router(config-if) #exit
Router(config) # ip dhcp excluded-address 10.3.0.1 Router(config) # ip dhcp pool Telephony
Router(dhop-config) # network 10.3.0.0 255.255.255.0 Router(dhop-config) #default-router 10.3.0.1
Router(dhcp-config)#option 150 ip 10.3.0.1
Router(dhcp-config)#
Router(dhcp-config) #exit
Router(config) #telephony-service
Router(config-telephony) # max-ephones 10
Router(config-telephony) # max-dn 10
Router(config-telephony) # p source-address 10.3.0.1 port 2000
Router(config-telephony) # auto assign 1 to 10
Router(config-telephony) # ephone-dn 1
Router(config-ephone-dn) #%LINK-3-UPDOWN: Interface ephone_dsp DN 1.1, changed state to up
Router(config-ephone-dn)#number 101
Router(config-ephone-dn)  # ephone-dn 2  Router(config-ephone-dn)  #%LINK-3-UPDOWN: Interface ephone_dsp DN 2.1, changed state to up
Router(config-ephone-dn)#
%IPPHONE-6-REGISTER: ephone-1 IP:10.3.0.2 Socket:2 DeviceType:Phone has registered.
Router(config-ephone-dn) #number 102
```

```
Router (config-ephone-dn) #exit
Router(config) # ephone 1
Router(config-ephone) #mac-address 0009.7C34.3C01
ephone slot is already registered with 0001.97B1.2001
Cannot change MAC address.
Router(config-ephone) #type ata
Router(config-ephone) #button 1:1
Dn already assigned.
Router (config-ephone) #exit
Router(config) # ephone 2
Router(config-ephone) # mac-address 000C.CF09.D862
Router(config-ephone) # type 7960
Router (config-ephone) #button 1:2
Router (config-ephone) #exit'
% Invalid input detected at '^' marker.
Router (config-ephone) #exit
Router(config) # ephone 3
Router(config-ephone) # mac-address 0006.2A28.7710
Router(config-ephone) #type CIPC
Router(config-ephone) #button 1:3
 dn 3 does not exist
Router(config-ephone)#
Router(config) #ephone 4
Router(config-ephone) #mac-address 0050.0F7F.720E
Router(config-ephone) #type CIPC
Router(config-ephone) #button 1:4
dn 4 does not exist
Router (config-ephone) #EXIT
Router (config) #ephone 5
Router(config-ephone) #mac-address 00D0.97BC.097D
Router(config-ephone) #type CIPC
Router(config-ephone) #button 1:5
 dn 5 does not exist
Router (config-ephone) #EXIT
Router(config) #ephone 6
Router(config-ephone) #mac-address 0006.2AD7.662E
Router(config-ephone) #type CIPC
Router(config-ephone) #button 1:6
 dn 6 does not exist
Router(config-ephone) #EXIT
```