COBOL Intrinsic Functions Cheatsheet

1. String Handling Functions

FUNCTION LENGTH(string) - Returns total length including spaces.

FUNCTION TRIM(string) - Removes leading and trailing spaces.

FUNCTION UPPER-CASE(string) - Converts string to uppercase.

FUNCTION LOWER-CASE(string) - Converts string to lowercase.

FUNCTION REVERSE(string) - Reverses the string.

FUNCTION CHAR(n) - Returns character for ASCII value n.
FUNCTION ORD(string) - Returns ASCII value of first character.

2. Mathematical Functions

FUNCTION ABS(x) - Absolute value.

FUNCTION MOD(x, y) - Modulo (remainder).

FUNCTION REM(x, y) - Remainder. FUNCTION SQRT(x) - Square root.

FUNCTION EXP(x) - e raised to power x.
FUNCTION LOG(x) - Natural logarithm.

FUNCTION FACTORIAL(n) - Returns factorial of n.

FUNCTION RANDOM(x) - Returns pseudo-random number.

3. Date and Time Functions

FUNCTION CURRENT-DATE - Current date & time (YYYYMMDDHHMISS+HHMM).

FUNCTION DATE-OF-INTEGER(n) - Converts integer to date.

FUNCTION INTEGER-OF-DATE(date) - Converts date to integer.

FUNCTION DAY-OF-WEEK(date) - Returns weekday number (1 = Monday).

4. Conversion and Formatting

FUNCTION NUMVAL(string) - Converts numeric string to number.

FUNCTION NUMVAL-C(string) - Handles currency symbols.

FUNCTION STRING-TO-HEX(string) - Converts string to hexadecimal.

FUNCTION HEX-TO-STRING(hex) - Converts hex to string.

FUNCTION ORD-MAX(string) - Max ASCII value in string.

5. Statistical / Aggregate Functions

FUNCTION MEAN(...) - Average value.

FUNCTION MEDIAN(...) - Median of numbers.

FUNCTION VARIANCE(...) - Variance of values.

FUNCTION STANDARD-DEVIATION(...) - Standard deviation.

6. Common Examples

MOVE FUNCTION TRIM(" COBOL ") TO WS-RESULT.

MOVE FUNCTION LENGTH(WS-NAME) TO WS-LEN.

MOVE FUNCTION CURRENT-DATE TO WS-DATE.