

R1

PhysicalConfigCLIAttributes

IOS Command Line Interface

```
icmp 209.165.200.226:27192.16.1.4:27      209.165.200.1:27      209.165.200.1:27
icmp 209.165.200.226:28192.16.1.4:28      209.165.200.1:28      209.165.200.1:28

R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#no ip nat inside source list 1 pool PUBLIC_ACCESS overload
R1(config)#no ip nat pool PUBLIC_ACCESS
R1(config)#ip nat inside source list 1 interface g0/0/0 overload
R1(config)#ex
R1#
%SYS-5-CONFIG_I: Configured from console by console

R1#sh ip nat translation
Pro  Inside global      Inside local      Outside local      Outside global
icmp 209.165.200.230:17192.16.1.3:17      209.165.200.1:17      209.165.200.1:17
icmp 209.165.200.230:18192.16.1.3:18      209.165.200.1:18      209.165.200.1:18
icmp 209.165.200.230:19192.16.1.3:19      209.165.200.1:19      209.165.200.1:19
icmp 209.165.200.230:20192.16.1.3:20      209.165.200.1:20      209.165.200.1:20
icmp 209.165.200.230:21192.16.1.2:21      209.165.200.1:21      209.165.200.1:21
icmp 209.165.200.230:22192.16.1.2:22      209.165.200.1:22      209.165.200.1:22
icmp 209.165.200.230:23192.16.1.2:23      209.165.200.1:23      209.165.200.1:23
icmp 209.165.200.230:24192.16.1.2:24      209.165.200.1:24      209.165.200.1:24
icmp 209.165.200.230:29192.16.1.4:29      209.165.200.1:29      209.165.200.1:29
icmp 209.165.200.230:30192.16.1.4:30      209.165.200.1:30      209.165.200.1:30
icmp 209.165.200.230:31192.16.1.4:31      209.165.200.1:31      209.165.200.1:31
icmp 209.165.200.230:32192.16.1.4:32      209.165.200.1:32      209.165.200.1:32

R1#
```

CopyPaste

R1

PhysicalConfigCLIAttributes

IOS Command Line Interface

```
R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#no ip nat inside source list 1 pool PUBLIC_ACCESS
^
% Invalid input detected at '^' marker.

R1(config)#ip nat inside source list 1 pool PUBLIC_ACCESS overload
R1(config)#ex
R1#
%SYS-5-CONFIG_I: Configured from console by console

R1#sh ip nat translation
Pro  Inside global      Inside local      Outside local      Outside global
icmp 209.165.200.226:13192.16.1.3:13      209.165.200.1:13      209.165.200.1:13
icmp 209.165.200.226:14192.16.1.3:14      209.165.200.1:14      209.165.200.1:14
icmp 209.165.200.226:15192.16.1.3:15      209.165.200.1:15      209.165.200.1:15
icmp 209.165.200.226:16192.16.1.3:16      209.165.200.1:16      209.165.200.1:16
icmp 209.165.200.226:17192.16.1.2:17      209.165.200.1:17      209.165.200.1:17
icmp 209.165.200.226:18192.16.1.2:18      209.165.200.1:18      209.165.200.1:18
icmp 209.165.200.226:19192.16.1.2:19      209.165.200.1:19      209.165.200.1:19
icmp 209.165.200.226:20192.16.1.2:20      209.165.200.1:20      209.165.200.1:20
icmp 209.165.200.226:25192.16.1.4:25      209.165.200.1:25      209.165.200.1:25
icmp 209.165.200.226:26192.16.1.4:26      209.165.200.1:26      209.165.200.1:26
icmp 209.165.200.226:27192.16.1.4:27      209.165.200.1:27      209.165.200.1:27
icmp 209.165.200.226:28192.16.1.4:28      209.165.200.1:28      209.165.200.1:28

R1#
```

CopyPaste

R1

Physical

Config

CLI

Attributes

IOS Command Line Interface

```
icmp 209.165.200.230:30192.16.1.4:30      209.165.200.1:30      209.165.200.1:30
icmp 209.165.200.230:31192.16.1.4:31      209.165.200.1:31      209.165.200.1:31
icmp 209.165.200.230:32192.16.1.4:32      209.165.200.1:32      209.165.200.1:32

R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#ip nat inside source static 192.16.1.2 209.165.200.229
R1(config)#ex
R1#
%SYS-5-CONFIG_I: Configured from console by console

R1#sh ip nat translation
Pro  Inside global      Inside local      Outside local      Outside global
icmp 209.165.200.229:25192.16.1.2:25      209.165.200.1:25      209.165.200.1:25
icmp 209.165.200.229:26192.16.1.2:26      209.165.200.1:26      209.165.200.1:26
icmp 209.165.200.229:27192.16.1.2:27      209.165.200.1:27      209.165.200.1:27
icmp 209.165.200.229:28192.16.1.2:28      209.165.200.1:28      209.165.200.1:28
icmp 209.165.200.230:21192.16.1.3:21      209.165.200.1:21      209.165.200.1:21
icmp 209.165.200.230:22192.16.1.3:22      209.165.200.1:22      209.165.200.1:22
icmp 209.165.200.230:23192.16.1.3:23      209.165.200.1:23      209.165.200.1:23
icmp 209.165.200.230:24192.16.1.3:24      209.165.200.1:24      209.165.200.1:24
icmp 209.165.200.230:33192.16.1.4:33      209.165.200.1:33      209.165.200.1:33
icmp 209.165.200.230:34192.16.1.4:34      209.165.200.1:34      209.165.200.1:34
icmp 209.165.200.230:35192.16.1.4:35      209.165.200.1:35      209.165.200.1:35
icmp 209.165.200.230:36192.16.1.4:36      209.165.200.1:36      209.165.200.1:36
--- 209.165.200.229      192.16.1.2      ---      ---

R1#
```

Copy

Paste