

ROUTER

```
ROUTER#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
ROUTER(config)#hostname SNRouter
SNRouter(config)#int e0/0
SNRouter(config-if)#ip add 50.0.0.1 255.0.0.0
SNRouter(config-if)#no sh
SNRouter(config-if)#ex
SNRouter(config)#
SNRouter(config)#username sathish pass 143
SNRouter(config)#line console 0
SNRouter(config-line)#login local
SNRouter(config-line)#ex
% Ambiguous command:  "ex"
SNRouter(config-line)#exit
SNRouter(config)#
SNRouter(config)#enable secret 1432
SNRouter(config)#
SNRouter(config)#line vty 0 4
SNRouter(config-line)#transport input telnet
SNRouter(config-line)#login local
SNRouter(config-line)#exit
SNRouter(config)#
```

ROUTER

```
% Ambiguous command: "ex"
SNRouter(config-line)#exit
SNRouter(config)#
SNRouter(config)#enable secret 1432
SNRouter(config)#
SNRouter(config)#line vty 0 4
SNRouter(config-line)#transport input telnet
SNRouter(config-line)#login local
SNRouter(config-line)#exit
SNRouter(config)#exit
SNRouter#
*Jul 11 10:13:34.247: %SYS-5-CONFIG_I: Configured from console by console
SNRouter#sh ip int brief
Interface                IP-Address      OK? Method Status    Prot
ocol
Ethernet0/0               50.0.0.1        YES manual up
Ethernet0/1               unassigned      YES TFTP   down
Ethernet0/2               unassigned      YES TFTP   down
Ethernet0/3               unassigned      YES TFTP   down
SNRouter#
```

```
ROUTER#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
ROUTER(config)#hostname SNRouter
SNRouter(config)#int e0/0
SNRouter(config-if)#ip add 50.0.0.1 255.0.0.0
SNRouter(config-if)#no sh
SNRouter(config-if)#ex
SNRouter(config)#
SNRouter(config)#username sathish pass l43
SNRouter(config)#line console 0
SNRouter(config-line)#login local
SNRouter(config-line)#ex
% Ambiguous command:  "ex"
SNRouter(config-line)#exit
SNRouter(config)#
SNRouter(config)#enable secret l432
SNRouter(config)#
SNRouter(config)#line vty 0 4
SNRouter(config-line)#transport input telnet
SNRouter(config-line)#login local
SNRouter(config-line)#exit
SNRouter(config)#exit
SNRouter#
*Jul 11 10:13:34.247: %SYS-5-CONFIG_I: Configured from console by console
SNRouter#sh ip int brief
Interface                IP-Address      OK? Method Status  Prot
-----
o0c1
Ethernet0/0              50.0.0.1        YES manual up      up
Ethernet0/1              unassigned      YES TFTP  down    down
Ethernet0/2              unassigned      YES TFTP  down    down
Ethernet0/3              unassigned      YES TFTP  down    down

SNRouter#
SNRouter#
```

QEMU (Win)

50.0.0.1 - PuTTY

```
User Access Verification

Username: sathish
Password:
SNRouter>
SNRouter>
SNRouter>
SNRouter>sh ip int brief
Interface                IP-Address      OK? Method Status      Prot
ocol
Ethernet0/0              50.0.0.1        YES manual  up          up
Ethernet0/1              unassigned      YES TFTP    down        down
Ethernet0/2              unassigned      YES TFTP    down        down
Ethernet0/3              unassigned      YES TFTP    down        down

SNRouter>en
Password:
SNRouter#
SNRouter#
```