




R1

```
*Aug 13 13:34:58.968: %LINEPROTO-5-UPDOWN: Line protocol on Interface
Ethernet0/0, changed state to down
R1(config-if)#
R1(config-if)#
R1(config-if)#
R1(config-if)#
R1(config-if)#no sh
R1(config-if)#
*Aug 13 13:36:02.881: %LINK-3-UPDOWN: Interface Ethernet0/0, changed s
tate to up
*Aug 13 13:36:03.881: %LINEPROTO-5-UPDOWN: Line protocol on Interface
Ethernet0/0, changed state to up
R1(config-if)#
*Aug 13 13:36:23.881: %HSRP-5-STATECHANGE: Ethernet0/0 Grp 1 state Spe
ak -> Standby
R1(config-if)#
*Aug 13 13:37:13.623: %HSRP-5-STATECHANGE: Ethernet0/0 Grp 1 state Sta
ndby -> Active
R1(config-if)#do sh standby br
P indicates configured to preempt.
|
Interface      Grp  Pri  P  State      Active      Standby      Virtual IP
Et0/0          1    100      Active  local      unknown     10.0.0.5
R1(config-if)#
```

R1 ACTIVE

PRIORITY VALUE 100



R2



```
|
Interface      Grp  Pri P State      Active      Standby      Virtual IP
Et0/0          1   110   Active local      unknown      10.0.0.5
R2(config)#do sh standby br
                P indicates configured to preempt.
                |
Interface      Grp  Pri P State      Active      Standby      Virtual IP
Et0/0          1   110   Active local      10.0.0.1      10.0.0.5
R2(config)#int e0/0
R2(config-if)#sh
R2(config-if)#
*Aug 13 13:37:13.624: %HSRP-5-STATECHANGE: Ethernet0/0 Grp 1 state Active -> Init
R2(config-if)#
*Aug 13 13:37:15.623: %LINK-5-CHANGED: Interface Ethernet0/0, changed state to administratively down
*Aug 13 13:37:16.623: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/0, changed state to down
R2(config-if)#do sh standby br
                P indicates configured to preempt.
                |
Interface      Grp  Pri P State      Active      Standby      Virtual IP
Et0/0          1   110   Init      unknown      unknown      10.0.0.5
R2(config-if)#
```

C:\WINDOWS\system32\cmd.exe

```
Reply from 40.0.0.1: bytes=32 time=2ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=2ms TTL=254
Reply from 40.0.0.1: bytes=32 time=2ms TTL=254
Reply from 40.0.0.1: bytes=32 time=2ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=3ms TTL=254
Reply from 40.0.0.1: bytes=32 time=2ms TTL=254
Reply from 40.0.0.1: bytes=32 time=2ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=2ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=2ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
```

**TRAFFIC GOES
WITHOUT DROPPING**



R2




```
R2 (config) #
R2 (config) #
R2 (config) #int e0/0
R2 (config-if) #standby 1 preempt
R2 (config-if) #ex
R2 (config) #
R2 (config) #
R2 (config) #
R2 (config) #int e0/0
R2 (config-if) #no sh
R2 (config-if) #e
*Aug 13 13:42:50.213: %HSRP-5-STATECHANGE: Ethernet0/0 Grp 1 state Listen -> Active
R2 (config-if) #ex
R2 (config) #
*Aug 13 13:42:51.165: %LINK-3-UPDOWN: Interface Ethernet0/0, changed state to up
*Aug 13 13:42:52.165: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/0, changed state to up
R2 (config) #do sh standby br
                P indicates configured to preempt.
                |
Interface      Grp  Pri P State      Active      Standby      Virtual IP
Et0/0          1   110 P Active     local       10.0.0.1     10.0.0.5
R2 (config) #
```

R2 ACTIVE**PRIORITY 110****RETURN AFTER FAILURE****PREEMPTION ENBALED**



R1



```
R1(config)#int e0/0
R1(config-if)#standby 1 preempt
R1(config-if)#
R1(config-if)#
R1(config-if)#
R1(config-if)#
R1(config-if)#ex
R1(config)#
R1(config)#
R1(config)#do sh standby br
```

**R1 REMAINS STANDBY
PRIORITY 100
PREEMPTION ENBALED**

P indicates configured to preempt.
|

Interface	Grp	Pri	P	State	Active	Standby	Virtual IP
Et0/0	1	100	P	Active	local	unknown	10.0.0.5

```
R1(config)#
*Aug 13 13:42:50.214: %HSRP-5-STATECHANGE: Ethernet0/0 Grp 1 state Active -> Speak
R1(config)#
*Aug 13 13:43:01.972: %HSRP-5-STATECHANGE: Ethernet0/0 Grp 1 state Speak -> Standby
```

```
R1(config)#do sh standby br
P indicates configured to preempt.
|
```

Interface	Grp	Pri	P	State	Active	Standby	Virtual IP
Et0/0	1	100	P	Standby	10.0.0.2	local	10.0.0.5

```
R1(config)#
```

C:\WINDOWS\system32\cmd.exe

```
Reply from 40.0.0.1: bytes=32 time=2ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=2ms TTL=254
Reply from 40.0.0.1: bytes=32 time=2ms TTL=254
Reply from 40.0.0.1: bytes=32 time=2ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=3ms TTL=254
Reply from 40.0.0.1: bytes=32 time=2ms TTL=254
Reply from 40.0.0.1: bytes=32 time=2ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=2ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=2ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
Reply from 40.0.0.1: bytes=32 time=1ms TTL=254
```

**TRAFFIC GOES
WITHOUT DROPPING**


```
R1(config-if)#standby 1 track 1
```

```
R1(config-if)#standby 1 track 1 decrement 20
```

```
R1(config-if)#ex
```

```
R1(config)#
```

```
R1(config)#
```

```
R1(config)#
```

```
R1(config)#
```

```
*Aug 13 14:23:33.284: %HSRP-5-STATECHANGE: Ethernet0/0 Grp 1 state Standby -> Active
```

```
R1(config)#
```

```
*Aug 13 14:24:03.262: %HSRP-5-STATECHANGE: Ethernet0/0 Grp 1 state Active -> Speak
```

```
R1(config)#
```

```
*Aug 13 14:24:14.009: %HSRP-5-STATECHANGE: Ethernet0/0 Grp 1 state Speak -> Standby
```

```
R1(config)#do sh stanby br
```

```
^
```

```
% Invalid input detected at '^' marker.
```

```
R1(config)#do sh standby br
```

```
P indicates configured to preempt.
```

```
|
```

Interface	Grp	Pri	P	State	Active	Standby	Virtual IP
-----------	-----	-----	---	-------	--------	---------	------------

R2

*Aug 13 14:23:33.289: %HSRP-5-STATECHANGE: Ethernet0/0 Grp 1 state Active -> Speak

*Aug 13 14:23:33.786: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/1, changed state to down

R2(config-if)#

*Aug 13 14:23:43.469: %HSRP-5-STATECHANGE: Ethernet0/0 Grp 1 state Speak -> Standby

R2(config-if)#no sh

R2(config-if)#

*Aug 13 14:24:00.902: %TRACK-6-STATE: 1 interface Et0/1 line-protocol Down -> Up

R2(config-if)#

*Aug 13 14:24:02.898: %LINK-3-UPDOWN: Interface Ethernet0/1, changed state to up

R2(config-if)#

*Aug 13 14:24:03.261: %HSRP-5-STATECHANGE: Ethernet0/0 Grp 1 state Standby -> Active

*Aug 13 14:24:03.898: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/1, changed state to up

R2(config-if)#ex

R2(config)#do sh standby br

P indicates configured to preempt.

Interface	Grp	Pri	P	State	Active	Standby	Virtual IP
Et0/0	1	110	P	Active	local	10.0.0.1	10.0.0.5

R2(config)#

**HSRP TRACKING ENABLED
R2 REMAINS ACTIVE**