

## 5) Edit Cell Content

### A) Fill in the blanks with the help of given word.

- 1) To completely change the content of a cell, select the cell, type in the new data and then press **Enter**.
- 2) To select all the cells in the worksheet, press **Ctrl + A**.
- 3) Making changes in the data entered in a worksheet is called **editing** the worksheet.
- 4) **Range** allows working with a number of cells at once.
- 5) To select non-adjacent rows or columns, press the **Ctrl** as you click each row columns header.

### B) Tick THE CORRCET

- 1) Which keyboard stroke will help you edit the cell contents?

Ans: F2

- 2) The default column width is ..... Characters.

Ans: 8.43

- 3) If the row height is set to ..... the row is hidden.

Ans: 0

- 4) Identify the option used to insert a column in the Cells group on the Home tab.

Ans: Insert ➡ Insert Sheet Columns

- 5) To accept the changes ,made to a cell, press:

Ans: Enter

### C) State True or False.

- 1) To select the contents in cell, single-click inside the cell. **False**
- 2) The range A2:A20 is the range of cells from A1 to A9. **False**
- 3) You cannot change the row height and column width to fit in the contents. **False**
- 4) Overwriting is the process of completely changing the contents of a cell. **True**

5) The live Preview feature of excel 2016 allows you to see how the contents will look with different Paste options before you actually paste it. **True**

**D) Answer the following question.**

1. What do you understand by the term editing a worksheet?

**Ans:**

Editing a worksheet means making changes in the cell contents. You can edit in two ways, either by overwriting or by partial modification.

2. Differentiate between the two types of editing cell contents: completely and partially.

**Ans:**

|                                                                                                 |                                                                                                                        |
|-------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------|
| <b>Completely:</b> This is called overwriting and it completely changes the contents of a cell. | <b>Partially:</b> This is called partial modification and it partially changes the contents of the cell.               |
| Select the cell and type the new data.<br>Press the Enter key.                                  | Select the cell. Double-click inside the cell or click in the formula bar.<br>Change the data and press the Enter key. |

3. What are the different ways of copying and moving cell contents?

**Ans:**

To copy/cut and paste cell contents, follow the steps:

Step 1: Select the cell or range of cells to be copied.

Step 2: On the **Home** tab, in the **Clipboard** group, click **Copy/Cut**.

Step 3: Click the cell where you want to paste the cells.

Step 4: On the **Home** tab, in the **Clipboard** group, click **Paste**.

Or position the mouse pointer at the lower border of the selected range of cells. Press **Ctrl** key to avoid auto fill series.

4. Describe the method of inserting non-adjacent rows/columns.

To insert non-adjacent rows/columns, hold down the **Ctrl** key while you select non-adjacent rows/columns.

5. Write three different ways to change row height and column width.

**Ans:**

The three different ways to change row height and column width are described below.

**USING THE AUTOFIT OPTION**

Step 1: Select the row(s) or column(s) that you want to change.

Step 2: On the **Home** tab, in the **Cells** group, click **Format**.

Step 3: Under **Cell Size**, click **AutoFit Row Height/AutoFit Column Width**.

**TO A SPECIFIC VALUE**

Step 1: Select the row(s) or column(s) that you want to change.

Step 2: On the **Home** tab, in the **Cells** group, click **Format**.

Step 3: Under **Cell Size**, click **Row Height/Column Width**.

Step 4: In the **Row Height/Column Width** box, type the value that you want. The row height or column width will adjust to the specified value.

**CHANGING ROW HEIGHT AND COLUMN WIDTH USING A MOUSE**

To change the height of row(s) using a mouse, drag the boundary below the row heading until the row has the height that you want.

To change the width of column(s) using a mouse, drag the boundary to the right side of the column heading until the column has the width that you want.