


INSTITUT UNIVERSITAIRE DES SCIENCES

INNOCENT COFFY MANAHENN

TD ReseauI #6

L3

FST



PC1

Physical Config Desktop Programming Attributes

IP Configuration

Interface FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address

Subnet Mask

Default Gateway 0.0.0.0

DNS Server 0.0.0.0

IPv6 Configuration

☒ Automatic ☐ Static

IPv6 Address 2001:DB8:1:0:201:97FF:FE80:7C6E / 64

Link Local Address FE80::201:97FF:FE80:7C6E

Default Gateway FE80::201:64FF:FEAD:4D01

DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5



Username

Password

Top

Meraki-Server

Toggle PDU List Window



PC2

Physical Config Desktop Programming Attributes

IP Configuration

Interface FastEthernet0

IP Configuration

☒ DHCP ☐ Static DHCP request successful.

IPv4 Address 192.168.1.3

Subnet Mask 255.255.255.0

Default Gateway 192.168.1.1

DNS Server 8.8.8.8

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address

Link Local Address FE80:20196FF:FE87:7E

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5

Username

Password

Top

Automatically Choose Connection Type

Toggle PDU List Window

PC3

Physical Config Desktop Programming Attributes

IP Configuration

Interface FastEthernet0

IP Configuration

☒ DHCP ☐ Static DHCP request successful.

IPv4 Address 192.168.1.4

Subnet Mask 255.255.255.0

Default Gateway 192.168.1.1

DNS Server 8.8.8.8

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address

Link Local Address FE80:290:CFF:FE09:56CA

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5

Username

Password

Top

Automatically Choose Connection Type

Toggle PDU List Window

PC4

Physical Config Desktop Programming Attributes

IP Configuration

Interface FastEthernet0

IP Configuration

☒ DHCP ☐ Static DHCP request successful.

IPv4 Address 192.168.1.5

Subnet Mask 255.255.255.0

Default Gateway 192.168.1.1

DNS Server 8.8.8.8

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address

Link Local Address FE80::20A:F3FF:FE16:D160

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5

Username

Password

Top

Automatically Choose Connection Type

Toggle PDU List Window

PC1

Physical Config Desktop Programming Attributes

IP Configuration

Interface FastEthernet0

IP Configuration

☒ DHCP ☐ Static DHCP request successful.

IPv4 Address 192.168.1.7

Subnet Mask 255.255.255.0

Default Gateway 192.168.1.1

DNS Server 8.8.8.8

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address

Link Local Address FE80::202:17FF:FE02:2513

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5

Username

Password

Top

Automatically Choose Connection Type

Toggle PDU List Window

Laptop0

Physical Config Desktop Programming Attributes

IP Configuration

Interface FastEthernet0

IP Configuration

☒ DHCP ☐ Static DHCP request successful.

IPv4 Address 192.168.1.8

Subnet Mask 255.255.255.0

Default Gateway 192.168.1.1

DNS Server 8.8.8.8

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address

Link Local Address FE80::203:E4FF:FE28:E02E

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5

Username

Password

Top

Automatically Choose Connection Type

Toggle PDU List Window

File Edit Options View Tools Extensions Window Help

Logical Physical x: 1320, y: 321

Root 02:02:30

ADMIN

PC-PT PC0

2960-24TT Switch1

NetworkController PT-Controller0

IUS

2911 Router1

2960-24TT Switch0

Repeater-PT Repeater0

Repeater-PT Repeater1

2960-24TT Switch2

PC-PT PC1

Laptop-PT Laptop0

2960-24TT Switch3

PC-PT PC2

PC-PT PC3

PC-PT PC4

PC-PT PC5

Printer-PT Printer0

2960-24TT Switch4

2960-24TT Switch5

2960-24TT Switch6

Server-PT Server2

Server-PT Server3

Server-PT Server1

Home-VoIP-PT Home VoIP0

Server-PT

Time: 00:50:53

Realtime Simulation


Scenario 0

New Delete

Toggle PDU List Window

Fire	Last Status	Source	Destination	Type	Color	Time(sec)	Periodic	Num	Edit	Delete
------	-------------	--------	-------------	------	-------	-----------	----------	-----	------	--------

Automatically Choose Connection Type



Router1

Physical Config CLI Attributes

IOS Command Line Interface

```

Press RETURN to get started!

Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface f0/0
Router(config-if)#ip address 192.168.1.1 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-6-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
Router(config-if)#exit
Router(config)#interface f0/1
Router(config-if)#ip address 192.168.2.1 255.255.255.0
Router(config-if)#no shutdown


Router(config-if)#
%LINK-6-CHANGED: Interface FastEthernet0/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up
Router(config-if)#exit
Router(config)#ip dhcp pool ADMIN
Router(dhcp-config)#network 192.168.1.0 255.255.255.0
Router(dhcp-config)#default-router 192.168.1.1
Router(dhcp-config)#dns-server 8.8.8.8
Router(dhcp-config)#exit
Router(config)#ip dhcp pool IUS
Router(dhcp-config)#network 192.168.2.0 255.255.255.0
Router(dhcp-config)#default-router 192.168.2.1
Router(dhcp-config)#dns-server 8.8.8.8
Router(dhcp-config)#exit
Router(config)#ip dhcp excluded-address 192.168.1.1 192.168.1.2
Router(config)#ip dhcp excluded-address 192.168.2.1 192.168.2.2
Router(config)#
  
```

Copy Paste

Top

Automatically Choose Connection Type

Toggle PDU List Window



En conclusion j'ai appris à configurer une adresse IPv6 à partir d'un serveur et aussi en utilisant le routeur comme DHCP pour le faire automatiquement ce TD est d'une importance capitale pour la suite de mon apprentissage