DIGITAL EXPERIENCE MONITORING (ZDX)

03/24/2026

ZSCALER HELP PORTAL

Table of Contents

Managing ZDX API Keys 3

About API Key Management 7

©2026 Zscaler, Inc. All rights reserved.

Digital Experience Monitoring (ZDX)

Managing ZDX API Keys

After your API subscription is enabled, the ZDX API Key Management page is accessible to an admin role. From there, the admin can provision and display available API keys.

> If you need to obtain API keys or secrets to access Zscaler OneAPI endpoints, see About API Clients in ZIdentity.

The API Key Management page allows you to perform the following actions:

- Create a new API key.

  1. Go to **Administration > Authentication > API Key Management**.
  2. Click **Create New API Key**.
  3. Enter the required information:
     - **Name**: Enter the API key name.
     - **Select Role**: Select an admin role to be assigned the API key.



  4. Click **Create Key** to confirm, and the **API Key** window appears.
  5. Click **Copy** to copy the API Key ID or Key Secret, or click **Download** to download the JSON file. You need both the API Key ID and Key Secret for authentication.

©2026 Zscaler, Inc. All rights reserved.



6. Close the window.

View an API key.

1. Go to **Administration** > **Authentication** > **API Key Management**.
2. Click the **View** icon for a specific API key to open the **API Key** window.
3. You can:
   - Click **Copy** to copy the API Key ID.
   - Click **Copy** to copy the API Key Secret.
   - Click **Download** to download a JSON file of the API key.

©2026 Zscaler, Inc. All rights reserved.



Edit the API key.

1. Go to **Administration > Authentication > API Key Management**.
2. Click the **Edit** icon for a specific API key to open the **Edit API Key** window.
3. Edit the **Name** or choose a new role from the **Select Role** drop-down menu.
4. Click **Save** to confirm the changes.



Delete the API key.

The **Delete** action allows you to delete the specified API key.

©2026 Zscaler, Inc. All rights reserved.

To delete a specific API key:

1. Go to **Administration > Authentication > API Key Management**.
2. Click the **Delete** icon for a specific API key to open the **Delete API Key** window.
3. Click **Delete** to confirm the deletion.



To learn more, see About API Key Management.

©2026 Zscaler, Inc. All rights reserved.

Digital Experience Monitoring (ZDX)

About API Key Management

API Key Management is a repository for an organization to store created API keys for admin roles. An API key consists of an API Key ID and Secret. These two items are required for access to ZDX APIs.

API Key Management provides the following benefits and enables you to:

- Provide a repository of generated, authorized API keys for programmatic access to ZDX API.
- Maintain the configuration of API keys by creating, viewing, editing, or deleting the API keys as required.
- Identify the life cycle of an API key to maintain security.

If you need to obtain API keys or secrets to access Zscaler OneAPI endpoints, see About API Clients in ZIdentity.

About the API Key Management Page

On the API Key Management page (Administration > Authentication > API Key Management), you can do the following:

1. Create a new API key.
2. View a list of created API keys. For each API key, you can view:
   - **Name**: The name of the API key.
   - **Key ID**: The ID of the API key.
   - **Role**: The role the API key is assigned to.
   - **Created By**: The user name that created the API key.
   - **Last Updated On**: The timestamp of when the API key was last updated.
   - **Actions**: The View, Edit, and Delete actions that can be performed on the API key.
3. View an API key.
4. Edit an API key.
5. Delete an API key.

©2026 Zscaler, Inc. All rights reserved.



©2026 Zscaler, Inc. All rights reserved.