Seaglass Control Center™

One Download That Installs, Configures, and Operates the Forge Suite

A single installer that is also a living dashboard. One download lays down a private Java runtime and the Forge suite, connects the AI model you choose, runs the services, manages data, records exercises, and lets an operator chat with the agent — all from one window, with no Java or other runtime to install beforehand. It is built for people who would rather evaluate a running system in minutes than assemble one over an afternoon.

One installer

a private Java runtime and every component you pick

a single Windows installer of about 435 MB; no runtime needs to be on the machine first

One window

set up, configure, and operate

light onboarding while you set up, a dark dashboard once setup is done

Your model

four vendors, or your own hardware

Claude, OpenAI, Gemini, or Grok — or an OpenAI-compatible model server you run

What it is

The Forge suite's installer and its operations console in one application. It sets up ForgeMind™, ForgeGIS™ and ForgeData™, plus whichever of ForgeGIS Studio™, Seaglass Globe™, the ForgeRelay™ exercise recorder and the compute broker you choose, then starts them in the right order and watches them run.

New in 1.2.6

Remove a data source, or unpublish a shared one; cancel a sync, or a question in the Ask tab. Recordings replay on the Globe, with a six-platform DIS sample to try. A crashed Control Center gets ForgeMind, Studio and the Globe back on relaunch. A log for every service, frm and forgedata launchers, a keyless USGS 3DEP source, and each engine's MCP contract version on the Services tab.

Built for evaluation

No Java to install, no dependency hunt, no config files to hand-edit to get running. A bundled sample elevation dataset means the first elevation and slope answers need no download, and with a model server you run on the workstation — Ollama is the tested path — the agent needs no internet either. A built-in conversation test checks an install, a provider, or a local model end to end.

FROM DOWNLOAD TO FIRST RESULT

1. **Run one installer.** Accept the evaluation license, then install for everyone on the computer or just for yourself. Each account then runs its own short setup the first time it opens the Control Center.
2. **Pick your components.** The core three are always set up; add Studio, the Globe, ForgeRelay, and the compute broker as you need them, and change your choice later with Run setup again.
3. **Pass live preflight.** Before setup prepares anything it checks disk, memory, graphics, and ports; memory and graphics are advisories, and a port already in use is changed right there.
4. **Connect your model.** A vendor key is validated live (or saved unchecked on an offline machine), then kept in the Windows Credential Manager and never written to disk. A local model server is checked by asking the model to answer, or saved unchecked if it isn't running yet.
5. **Start the suite and ask.** One click starts everything you installed, in order; ForgeMind spawns ForgeGIS and ForgeData as MCP children, and the Ask tab shows the agent's tool calls live as it works, then the answer.

CONTINUED ON REVERSE →

THE SUITE IT MANAGES

COMPONENT	ROLE	LISTENS ON
ForgeMind	The agent: plans, calls the engines as MCP tools, answers	8080 · loopback + token
ForgeGIS	GPU geospatial engine, 239 operations (MCP child of ForgeMind)	stdio
ForgeData	Data catalog and ingesters (MCP child of ForgeMind)	stdio
ForgeGIS Studio ***(opt-in)***	Browser workspace: map, pipelines, batch, chat	8081 · loopback
Seaglass Globe ***(opt-in)***	The 3D view and the agent's drawing surface; needs a real GPU	7900 · loopback + token
ForgeRelay ***(opt-in)***	Records DIS and CoT exercise traffic into a scenario library	UDP 3000 · 6969, per config
Compute broker ***(opt-in)***	Job queue and GPU workers for raster batch jobs	8082 · this machine or a fleet

Record an exercise. ForgeRelay adds a Record tab. DIS traffic is recorded as ground truth and a CoT feed as one side's picture, never as truth, each into a GeoPackage scenario library that the Globe the dashboard starts replays, live while it records; a one-minute DIS sample of six synthetic platforms ships to try. The relay refuses to start until a person answers what the wire can't say — which force is which side, and the marking — and every stop ends in a verdict: complete, refused, or stopped with holes. HLA needs an RTI, which the suite doesn't include.

Hand the batch job to the GPUs. Ask ForgeMind for work like “hillshade every tile in this folder” and it becomes one job that GPU workers split between them, on this machine or across a fleet sharing one broker. A crashed worker is restarted and its task handed on; a task too large for any worker's GPU is refused from the raster's header, before any GPU work. ForgeGIS Studio sends its raster batches to the broker too, running locally whatever it can't send; the Globe runs its batch work locally.

Four vendors, or your own hardware. Connect Claude, OpenAI, Gemini, or Grok with an API key, validated live before it is stored — or point ForgeMind at an OpenAI-compatible model server you run, on the workstation or elsewhere on your network, so no model request goes to a cloud vendor. Ollama is the tested path; expect a local model to be slower than a hosted one. Set up several providers and choose which one ForgeMind starts with.

One install, every account. Install once for everyone on a workstation and each person sets up their own account, with their own keys and their own catalog. Beside it sits a read-only catalog for the whole machine; publishing a folder to it takes Administrator approval, so what everyone sees is curated.

Security posture. Local by default: the agent's API binds 127.0.0.1 behind a per-install token, and only components you turn on — the recorder's feed ports, a broker serving the fleet — listen beyond this machine. AI keys, data-source keys, and tokens live in the Windows Credential Manager, never on disk. The evaluation period runs 90 days from first install unless your evaluation agreement says otherwise; the About card in Settings shows where it stands. The third-party notices carry every licence text in full.

Evaluate the Forge suite — see it install and run on one machine

Windows x64; 8 GB of RAM recommended for the full suite, plus about 2 GB per compute worker; a GPU recommended, and Seaglass Globe needs a real, hardware-accelerated one. The Forge suite is commercially licensed; evaluation builds are available to qualified teams.

rich@seaglassfoundry.com · seaglassfoundry.com

Seaglass Control Center™, ForgeGIS™, ForgeMind™, ForgeData™, ForgeGIS Studio™, Seaglass Globe™, ForgeRelay™, and Seaglass Foundry™ are trademarks of Seaglass Foundry LLC. Windows, the Windows Credential Manager, Java, Claude, OpenAI, Gemini, Grok, Ollama, GeoPackage, and the Model Context Protocol are marks of their respective owners; reference to them does not imply endorsement. The Seaglass Control Center installs and operates the Forge suite and is not sold separately. © 2026 Seaglass Foundry LLC. All rights reserved.