JavaScript is disabled on your browser.



compact1, compact2, compact3

java.lang

# Class InheritableThreadLocal<T>

java.lang.Object
    java.lang.ThreadLocal<T>
        java.lang.InheritableThreadLocal<T>

---

```
public class InheritableThreadLocal<T>
extends ThreadLocal<T>
```

This class extends `ThreadLocal` to provide inheritance of values from parent thread to child thread: when a child thread is created, the child receives initial values for all inheritable thread-local variables for which the parent has values. Normally the child's values will be identical to the parent's; however, the child's value can be made an arbitrary function of the parent's by overriding the `childValue` method in this class.

Inheritable thread-local variables are used in preference to ordinary thread-local variables when the per-thread-attribute being maintained in the variable (e.g., User ID, Transaction ID) must be automatically transmitted to any child threads that are created.

**Since:**

`1.2`

**See Also:**

`ThreadLocal`

## *Constructor Summary*

**Constructors**

| Constructor | Description |
| --- | --- |

| InheritableThreadLocal() | |
|---|---|

## Method Summary

Concrete Methods

| Modifier and Type | Method | Description |
|---|---|---|
| protected T | childValue(T parentValue) | Computes the child's initial value for this inheritable thread-local variable as a function of the parent's value at the time the child thread is created. |

### Methods inherited from class java.lang.ThreadLocal

get, initialValue, remove, set, withInitial

### Methods inherited from class java.lang.Object

clone, equals, finalize, getClass, hashCode, notify, notifyAll, toString, wait, wait, wait

## Constructor Detail

### InheritableThreadLocal

```
public InheritableThreadLocal()
```

## Method Detail

### childValue

```
protected T childValue(T parentValue)
```

Computes the child's initial value for this inheritable thread-local variable as a function of the parent's value at the time the child thread is created. This method is called from within the parent thread before the child is started.

This method merely returns its input argument, and should be overridden if a different behavior is desired.

**Parameters:**

`parentValue - the parent thread's value`

**Returns:**

`the child thread's initial value`



Submit a bug or feature
For further API reference and developer documentation, see Java SE Documentation. That documentation contains more detailed, developer-targeted descriptions, with conceptual overviews, definitions of terms, workarounds, and working code examples.
Copyright © 1993, 2026, Oracle and/or its affiliates. All rights reserved. Use is subject to license terms.
Also see the documentation redistribution policy.

Scripting on this page tracks web page traffic, but does not change the content in any way.