JavaScript is disabled on your browser.

compact1, compact2, compact3

java.nio.file.attribute

Class AclEntry.Builder

java.lang.Object
    java.nio.file.attribute.AclEntry.Builder

Enclosing class:

AclEntry

```
public static final class AclEntry.Builder
extends Object
```

A builder of `AclEntry` objects.

A `Builder` object is obtained by invoking one of the `newBuilder` methods defined by the `AclEntry` class.

Builder objects are mutable and are not safe for use by multiple concurrent threads without appropriate synchronization.

Since:

1.7

Method Summary

Concrete Methods

Modifier and Type	Method	Description
`AclEntry`	`build()`	Constructs an `AclEntry` from the components

		of this builder.
AclEntry.Builder	setFlags(AclEntryFlag... flags)	Sets the flags component of this builder.
AclEntry.Builder	setFlags(Set<AclEntryFlag> flags)	Sets the flags component of this builder.
AclEntry.Builder	setPermissions(AclEntryPermission... perms)	Sets the permissions component of this builder.
AclEntry.Builder	setPermissions(Set<AclEntryPermission> perms)	Sets the permissions component of this builder.
AclEntry.Builder	setPrincipal(UserPrincipal who)	Sets the principal component of this builder.
AclEntry.Builder	setType(AclEntryType type)	Sets the type component of this builder.

Methods inherited from class java.lang.Object

clone, equals, finalize, getClass, hashCode, notify, notifyAll, toString, wait, wait, wait

Method Detail

build

`public AclEntry build()`

Constructs an `AclEntry` from the components of this builder. The type and who components are required to have been set in order to construct an `AclEntry`.

Returns:

a new ACL entry

Throws:

`IllegalStateException` - if the type or who component have not been set

setType

`public AclEntry.Builder setType(AclEntryType type)`

Sets the type component of this builder.

Parameters:

type - the component type

Returns:

this builder

setPrincipal

`public AclEntry.Builder setPrincipal(UserPrincipal who)`

Sets the principal component of this builder.

Parameters:

who - the principal component

Returns:

this builder

setPermissions

`public AclEntry.Builder setPermissions(Set<AclEntryPermission> perms)`

Sets the permissions component of this builder. On return, the permissions component of this builder is a copy of the given set.

Parameters:

`perms - the permissions component`

Returns:

`this builder`

Throws:

`ClassCastException - if the set contains elements that are not of type AclEntryPermission`

setPermissions

```
public AclEntry.Builder setPermissions(AclEntryPermission... perms)
```

Sets the permissions component of this builder. On return, the permissions component of this builder is a copy of the permissions in the given array.

Parameters:

`perms - the permissions component`

Returns:

`this builder`

setFlags

```
public AclEntry.Builder setFlags(Set<AclEntryFlag> flags)
```

Sets the flags component of this builder. On return, the flags component of this builder is a copy of the given set.

Parameters:

`flags - the flags component`

Returns:

`this builder`

Throws:

`ClassCastException - if the set contains elements that are not of type AclEntryFlag`

setFlags

```
public AclEntry.Builder setFlags(AclEntryFlag... flags)
```

Sets the flags component of this builder. On return, the flags component of this builder is a copy of the flags in the given array.

Parameters:

flags - the flags component

Returns:

this builder

Submit a bug or feature
For further API reference and developer documentation, see Java SE Documentation. That documentation contains more detailed, developer-targeted descriptions, with conceptual overviews, definitions of terms, workarounds, and working code examples.
Copyright © 1993, 2026, Oracle and/or its affiliates. All rights reserved. Use is subject to license terms.
Also see the documentation redistribution policy.

Scripting on this page tracks web page traffic, but does not change the content in any way.