JavaScript is disabled on your browser.

compact1, compact2, compact3

java.nio.file.attribute

Interface FileOwnerAttributeView

All Superinterfaces:

`AttributeView`, `FileAttributeView`

All Known Subinterfaces:

`AclFileAttributeView`, `PosixFileAttributeView`

```
public interface FileOwnerAttributeView
extends FileAttributeView
```

A file attribute view that supports reading or updating the owner of a file. This file attribute view is intended for file system implementations that support a file attribute that represents an identity that is the owner of the file. Often the owner of a file is the identity of the entity that created the file.

The `getOwner` or `setOwner` methods may be used to read or update the owner of the file.

The `getAttribute` and `setAttribute` methods may also be used to read or update the owner. In that case, the owner attribute is identified by the name `"owner"`, and the value of the attribute is a `UserPrincipal`.

Since:

1.7

Method Summary

Abstract Methods

Modifier and Type	Method	Description

UserPrincipal	**getOwner**()	Read the file owner.
String	**name**()	Returns the name of the attribute view.
void	**setOwner**(**UserPrincipal** owner)	Updates the file owner.

Method Detail

name

`String name()`

Returns the name of the attribute view. Attribute views of this type have the name `"owner"`.

Specified by:

`name` in interface `AttributeView`

Returns:

the name of the attribute view

getOwner

```
UserPrincipal getOwner()
                throws IOException
```

Read the file owner.

It it implementation specific if the file owner can be a `group`.

Returns:

the file owner

Throws:

`IOException` - if an I/O error occurs

`SecurityException` - In the case of the default provider, a security manager is installed, and it denies `RuntimePermission("accessUserInformation")` or its `checkRead` method denies read access to the file.

setOwner

```
void setOwner(UserPrincipal owner)
       throws IOException
```

Updates the file owner.

It it implementation specific if the file owner can be a `group`. To ensure consistent and correct behavior across platforms it is recommended that this method should only be used to set the file owner to a user principal that is not a group.

Parameters:

`owner - the new file owner`

Throws:

`IOException - if an I/O error occurs, or the owner parameter is a group and this implementation does not support setting the owner to a group`

`SecurityException - In the case of the default provider, a security manager is installed, and it denies RuntimePermission("accessUserInformation") or its checkWrite method denies write access to the file.`

Submit a bug or feature
For further API reference and developer documentation, see Java SE Documentation. That documentation contains more detailed, developer-targeted descriptions, with conceptual overviews, definitions of terms, workarounds, and working code examples.
Copyright © 1993, 2026, Oracle and/or its affiliates. All rights reserved. Use is subject to license terms.
Also see the documentation redistribution policy.

Scripting on this page tracks web page traffic, but does not change the content in any way.