JavaScript is disabled on your browser.

compact1, compact2, compact3

java.util.stream

Interface IntStream.Builder

All Superinterfaces:

IntConsumer

Enclosing interface:

IntStream

```
public static interface IntStream.Builder
extends IntConsumer
```

A mutable builder for an `IntStream`.

A stream builder has a lifecycle, which starts in a building phase, during which elements can be added, and then transitions to a built phase, after which elements may not be added. The built phase begins when the `build()` method is called, which creates an ordered stream whose elements are the elements that were added to the stream builder, in the order they were added.

Since:

1.8

See Also:

`IntStream.builder()`

Method Summary

Abstract Methods | Default Methods

Modifier and Type	Method	Description

void	**accept**(int t)	Adds an element to the stream being built.
default **IntStream.Builder**	**add**(int t)	Adds an element to the stream being built.
IntStream	**build**()	Builds the stream, transitioning this builder to the built state.

Methods inherited from interface java.util.function.IntConsumer

andThen

Method Detail

accept

```
void accept(int t)
```

Adds an element to the stream being built.

Specified by:

accept in interface IntConsumer

Parameters:

t - the input argument

Throws:

IllegalStateException - if the builder has already transitioned to the built state

add

```
default IntStream.Builder add(int t)
```

Adds an element to the stream being built.

Implementation Requirements:

The default implementation behaves as if:

```
    accept(t)
    return this;
```

Parameters:

`t - the element to add`

Returns:

`this builder`

Throws:

`IllegalStateException - if the builder has already transitioned to the built state`

build

`IntStream build()`

Builds the stream, transitioning this builder to the built state. An `IllegalStateException` is thrown if there are further attempts to operate on the builder after it has entered the built state.

Returns:

`the built stream`

Throws:

`IllegalStateException - if the builder has already transitioned to the built state`

Submit a bug or feature
For further API reference and developer documentation, see Java SE Documentation. That documentation contains more detailed, developer-targeted descriptions, with conceptual overviews, definitions of terms, workarounds, and working code examples.
Copyright © 1993, 2026, Oracle and/or its affiliates. All rights reserved. Use is subject to license terms.
Also see the documentation redistribution policy.

Scripting on this page tracks web page traffic, but does not change the content in any way.