JavaScript is disabled on your browser.

compact1, compact2, compact3

java.util.stream

Interface Stream.Builder<T>

Type Parameters:

`T - the type of stream elements`

All Superinterfaces:

`Consumer`<T>

Enclosing interface:

`Stream`<T>

```
public static interface Stream.Builder<T>
extends Consumer<T>
```

A mutable builder for a `Stream`. This allows the creation of a `Stream` by generating elements individually and adding them to the `Builder` (without the copying overhead that comes from using an `ArrayList` as a temporary buffer.)

A stream builder has a lifecycle, which starts in a building phase, during which elements can be added, and then transitions to a built phase, after which elements may not be added. The built phase begins when the `build()` method is called, which creates an ordered `Stream` whose elements are the elements that were added to the stream builder, in the order they were added.

Since:

`1.8`

See Also:

`Stream.builder()`

Method Summary

Abstract Methods

Default Methods

Modifier and Type	Method	Description
void	accept(T t)	Adds an element to the stream being built.
default Stream.Builder<T>	add(T t)	Adds an element to the stream being built.
Stream<T>	build()	Builds the stream, transitioning this builder to the built state.

Methods inherited from interface java.util.function.Consumer

andThen

Method Detail

accept

```
void accept(T t)
```

Adds an element to the stream being built.

Specified by:

accept in interface Consumer<T>

Parameters:

t - the input argument

Throws:

IllegalStateException - if the builder has already transitioned to the built state

add

```
default Stream.Builder<T> add(T t)
```

Adds an element to the stream being built.

Implementation Requirements:

The default implementation behaves as if:

```
accept(t)
return this;
```

Parameters:

`t` - the element to add

Returns:

this builder

Throws:

`IllegalStateException` - if the builder has already transitioned to the built state

build

`Stream<T> build()`

Builds the stream, transitioning this builder to the built state. An `IllegalStateException` is thrown if there are further attempts to operate on the builder after it has entered the built state.

Returns:

the built stream

Throws:

`IllegalStateException` - if the builder has already transitioned to the built state

Copyright © 1993, 2026, Oracle and/or its affiliates. All rights reserved. Use is subject to license terms.
Also see the documentation redistribution policy.

Scripting on this page tracks web page traffic, but does not change the content in any way.