JavaScript is disabled on your browser.

compact1, compact2, compact3

java.lang

Class Error

java.lang.Object
    java.lang.Throwable
        java.lang.Error

All Implemented Interfaces:

Serializable

Direct Known Subclasses:

AnnotationFormatError, AssertionError, AWTError, CoderMalfunctionError, FactoryConfigurationError, FactoryConfigurationError, IOError, LinkageError, SchemaFactoryConfigurationError, ServiceConfigurationError, ThreadDeath, TransformerFactoryConfigurationError, VirtualMachineError

---

```
public class Error
extends Throwable
```

An `Error` is a subclass of `Throwable` that indicates serious problems that a reasonable application should not try to catch. Most such errors are abnormal conditions. The `ThreadDeath` error, though a "normal" condition, is also a subclass of `Error` because most applications should not try to catch it.

A method is not required to declare in its `throws` clause any subclasses of `Error` that might be thrown during the execution of the method but not caught, since these errors are abnormal conditions that should never occur. That is, `Error` and its subclasses are regarded as unchecked exceptions for the purposes of compile-time checking of exceptions.

Since:

JDK1.0

See Also:

ThreadDeath, Serialized Form

See *The Java™ Language Specification*:

11.2 Compile-Time Checking of Exceptions

Constructor Summary

Constructors

Modifier	Constructor	Description
	`Error()`	Constructs a new error with `null` as its detail message.
	`Error(String message)`	Constructs a new error with the specified detail message.
	`Error(String message, Throwable cause)`	Constructs a new error with the specified detail message and cause.
protected	`Error(String message, Throwable cause, boolean enableSuppression, boolean writableStackTrace)`	Constructs a new error with the specified detail message, cause, suppression enabled or disabled, and writable stack trace enabled or disabled.
	`Error(Throwable cause)`	Constructs a new error with the specified cause and a detail message of `(cause==null ? null : cause.toString())` (which typically contains the class and detail message of `cause`).

Method Summary

Methods inherited from class java.lang.Throwable

addSuppressed, fillInStackTrace, getCause, getLocalizedMessage, getMessage, getStackTrace, getSuppressed, initCause, printStackTrace, printStackTrace, printStackTrace, setStackTrace, toString

Methods inherited from class java.lang.Object

clone, equals, finalize, getClass, hashCode, notify, notifyAll, wait, wait, wait

Constructor Detail

Error

```
public Error()
```

Constructs a new error with `null` as its detail message. The cause is not initialized, and may subsequently be initialized by a call to `Throwable.initCause(java.lang.Throwable)`.

Error

```
public Error(String message)
```

Constructs a new error with the specified detail message. The cause is not initialized, and may subsequently be initialized by a call to `Throwable.initCause(java.lang.Throwable)`.

Parameters:

`message - the detail message. The detail message is saved for later retrieval by the Throwable.getMessage() method.`

Error

```
public Error(String message,
             Throwable cause)
```

Constructs a new error with the specified detail message and cause.

Note that the detail message associated with `cause` is *not* automatically incorporated in this error's detail message.

Parameters:

message - the detail message (which is saved for later retrieval by the Throwable.getMessage() method).

cause - the cause (which is saved for later retrieval by the Throwable.getCause() method). (A null value is permitted, and indicates that the cause is nonexistent or unknown.)

Since:

1.4

Error

public Error(Throwable cause)

Constructs a new error with the specified cause and a detail message of (cause==null ? null : cause.toString()) (which typically contains the class and detail message of cause). This constructor is useful for errors that are little more than wrappers for other throwables.

Parameters:

cause - the cause (which is saved for later retrieval by the Throwable.getCause() method). (A null value is permitted, and indicates that the cause is nonexistent or unknown.)

Since:

1.4

Error

```
protected Error(String message,
                Throwable cause,
                boolean enableSuppression,
                boolean writableStackTrace)
```

Constructs a new error with the specified detail message, cause, suppression enabled or disabled, and writable stack trace enabled or disabled.

Parameters:

`message - the detail message.`

`cause - the cause. (A null value is permitted, and indicates that the cause is nonexistent or unknown.)`

`enableSuppression - whether or not suppression is enabled or disabled`

`writableStackTrace - whether or not the stack trace should be writable`

Since:

`1.7`

Submit a bug or feature
For further API reference and developer documentation, see Java SE Documentation. That documentation contains more detailed, developer-targeted descriptions, with conceptual overviews, definitions of terms, workarounds, and working code examples.
Copyright © 1993, 2026, Oracle and/or its affiliates. All rights reserved. Use is subject to license terms.
Also see the documentation redistribution policy.

Scripting on this page tracks web page traffic, but does not change the content in any way.