Api Authorization

Version	Created by	Department
1.0	Héctor Furió	Client Integrations

API Authorization Guide

To interact with CTT Express via API, the first step is to request an access token, which must be used with each API transaction. This token is valid for 24 hours, so it's essential to programmatically refresh it before expiration to maintain continuous access.

Please note that:

- You need to generate **only one single token every 24h**
- This token generated is **valid for any endpoint** of the CTT API

To improve capacities on CTT platform, it is mandatory to optimize the token generation and use.

Below, you will find a detailed guide on obtaining an authorized token by directly invoking the token API.

Obtain an Authorization Token

To get an authorization token, you need to make a POST request to the following endpoint:

URL:

- UAT: https://api-test.cttexpress.com/integrations/oauth2/token
- Production: https://api.cttexpress.com/integrations/oauth2/token

Request Details:

- **Method:** POST
- **Content Type:** application/x-www-form-urlencoded

Request Parameters:

- client_id (string): The client ID provided by CTT Express.
- client_secret (string): The client secret provided by CTT Express.
- grant_type (string): Set to client_credentials.
- scope (string): Set to urn:com:ctt-express:integration-clients:scopes:common/ALL.

Example Request Body:

```
curl --location 'https://api-test.cttexpress.com/integrations/oauth2/token' \

--header 'Content-Type: application/x-www-form-urlencoded' \

--data-urlencode 'client_id=Client_ID' \

--data-urlencode 'client_secret=Client-Secret' \

--data-urlencode 'scope=urn:com:ctt-express:integration-
clients:scopes:common/ALL' \

--data-urlencode 'grant_type=client_credentials'
```

Response:


```
{

    "access_token":
"eyJraWQiOiJDSXo4cU0xcmRxbmxUVlE2a2pydms2dE02WjRmYk53dzNYUk56VzNwOXdzPSIsImFs
ZyI6IlJTMjU2In0.eyJzdWIiOiIybjY5ZmNsaXVzM2F1NTJubWo5dWoxcWNmbiIsInRva2VuX3VzZ
SI6ImFjY2VzcyIsInNjb3BlIjoidXJuOmNvbTpjdHQtZXhwcmVzczppbnRlZ3JhdGlvbi1jbGllbn
RzOnNjb3Blczpjb21tb25cL0FMTCIsImF1dGhfdGltZSI6MTc0NzkyMjc1OSwiaXNzIjoiaHR0cHM
6XC9cL2NvZ25pdG8taWRwLmV1LXdlc3QtMS5hbWF6b25hd3MuY29tXC9ldS13ZXN0LTFfQzdkWUtt
NHFGIiwiZXhwIjoxNzQ4MDA5MTU5LCJpYXQiOjE3NDc5MjI3NTksInZlcnNpb24iOjIsImp0aSI6I
jdiMTJkNzY3LTczODQtNDJiNS1hOWY5LTM3OWM2NWJiNmQ1OSIsImNsaWVudF9pZCI6IjJuNjlmY2
xpdXMzYXU1Mm5tajl1ajFxY2ZuIn0.uqai0TVlG9bQ4B8v8IqXT5OFoASIYa3aVwHC2BIbBVmC7m5
hB8AWxSuyjIik06_VzmVn2w0pq97_TzZAwZR9fhiv15RE03RkDdijzSEs91P2T0POwCfBjNREaeBG
FDdXCvyhDdnaB0y0GOszGCFjV5GikKTq7wDvCbeqvXH7McJaD7tyFAs_-t1q9Q_ZClghpY_IQYX-
t7-
521f45u7HtCngkUsoQKxuzdjX3Du8QvqJlzDmhepb5B0RlxsU95_5tGdZyJhsDlQhgpCByu0pSQly
a9iB7ECTbMfa7yNR2F3DoYNrb8rwCcKKhcRdSjO2DxcfTXoAElB89yNDR-t6RS",

    "expires_in": 86400,

    "token_type": "Bearer"

}
```

API Catalog

Once you retrieved your token, you can then access different endpoints, in test and production.
Below are reported the base URLs that you will need to access the different services.

Base URLs:

- **Test Environment:** https://api-test.cttexpress.com/integrations
- **Production Environment:** https://api.cttexpress.com/integrations

For further information about each endpoint, please refer to the full API definition provided by CTT Express