

## Task Description:

Create a windows Vm machine in AWS and connect with RDP open CMD in windows share the about system info.

### Techstacks needs to be used :

- AWS EC2 (windows)
- RDP (Preavailable in Windows)

### ◆ Step 1 — Launch Windows EC2 Instance

#### 1 Login to AWS

- Go to: <https://console.aws.amazon.com>
- Open **EC2 Dashboard**
- Select your region

**Launch an instance** [Info](#)

Amazon EC2 allows you to create virtual machines, or instances, that run on the AWS Cloud. Quickly get started by following the simple steps below.

**Name and tags** [Info](#)

Name  
EC2 [Add additional tags](#)

**▼ Application and OS Images (Amazon Machine Image)** [Info](#)

An AMI contains the operating system, application server, and applications for your instance. If you don't see a suitable AMI below, use the search field or choose [Browse more AMIs](#).

Search our full catalog including 1000s of application and OS images

[AMI from catalog](#) Quick Start

**Name**  
Microsoft Windows Server 2022 Core Base [Verified provider](#) [Free tier eligible](#)

**Description**  
Microsoft Windows 2022 Datacenter Core edition. [English]

[Browse more AMIs](#)  
Including AMIs from AWS, Marketplace and

**▼ Summary**

**Number of instances** [Info](#)  
1

**Software Image (AMI)**  
Microsoft Windows Server 2022 ...[read more](#)  
ami-0a11422c21f02d40c

**Virtual server type (instance type)**  
t3.micro

**Firewall (security group)**  
New security group

**Storage (volumes)**  
1 volume(s) - 30 GiB

[Cancel](#) [Launch instance](#) [Preview code](#)

#### 2 Launch Instance


Click **Launch Instance**

### Basic Configuration:

- **Name:** Windows-VM
- **AMI (OS Image):**  
👉 Select **Microsoft Windows Server 2022 Base** (or 2019)
- **Instance Type:**  
👉 t2.micro (Free tier eligible)

### 3 Create Key Pair

- Click **Create new key pair**
- Name: windows-key
- Type: **RSA**
- Format: **.pem**



The screenshot shows the 'Create key pair' dialog box in the AWS Management Console. It has a title bar with a close button. The main content area is divided into sections: 'Key pair name' with a text input field containing 'Devopskey' and a note about character limits; 'Key pair type' with two radio button options, 'RSA' (selected) and 'ED25519'; and 'Private key file format' with two radio button options, '.pem' (selected) and '.ppk'. A yellow warning box at the bottom states: 'When prompted, store the private key in a secure and accessible location on your computer. You will need it later to connect to your instance. [Learn more](#)'. At the bottom right are 'Cancel' and 'Create key pair' buttons.

**Key pair name**  
Key pairs allow you to connect to your instance securely.  
Devopskey  
The name can include up to 255 ASCII characters. It can't include leading or trailing spaces.

**Key pair type**

☒ **RSA**  
RSA encrypted private and public key pair

☐ **ED25519**  
ED25519 encrypted private and public key pair (Not supported for Windows instances)

**Private key file format**

☒ **.pem**  
For use with OpenSSH

☐ **.ppk**  
For use with PuTTY

 When prompted, store the private key in a secure and accessible location on your computer. **You will need it later to connect to your instance.** [Learn more](#)

[Cancel](#) [Create key pair](#)

### 4 Network Settings

Ensure:

- ✓ Allow RDP Traffic
  - Protocol: TCP
  - Port: **3389**
  - Source: Anywhere

### Firewall (security groups) [Info](#)

A security group is a set of firewall rules that control the traffic for your instance. Add rules to allow specific traffic to reach your instance.

☒ Create security group

☐ Select existing security group

We'll create a new security group called 'launch-wizard-1' with the following rules:

☒ Allow RDP traffic from

Helps you connect to your instance

Anywhere

0.0.0.0/0

☐ Allow HTTPS traffic from the internet

To set up an endpoint, for example when creating a web server

☐ Allow HTTP traffic from the internet

To set up an endpoint, for example when creating a web server

 Rules with source of 0.0.0.0/0 allow all IP addresses to access your instance. We recommend setting security group rules to allow access from known IP addresses only. 


### ▼ Configure storage [Info](#)

[Advanced](#)

1x  GiB  Root volume, Not encrypted

## ◆ Step 2 — Get Windows Administrator Password

1. Select your instance
2. Click **Connect**



The screenshot shows the AWS Management Console interface for an EC2 instance. The breadcrumb navigation at the top indicates the path: EC2 > Instances > i-050d52934f9cd754c. On the left, a sidebar menu lists navigation options: Dashboard, AWS Global View, Events, Instances (selected), Instance Types, and Launch Templates. The main content area displays the 'Instance summary for i-050d52934f9cd754c (EC2)'. At the top right of the summary are three buttons: 'Connect', 'Instance state', and 'Actions'. The summary is updated 'less than a minute ago'. It is organized into three columns: 1. Instance ID: i-050d52934f9cd754c. 2. Public IPv4 address: 100.31.119.81 (with a link to 'open address'). 3. Private IPv4 addresses: 172.31.11.28. Below these, the 'Instance state' is shown as 'Running' with a green checkmark icon. At the bottom right, the 'Public DNS' is listed as 'ec2-100-31-119-81.compute-1.amazonaws.com' (with a link to 'open address').

Choose **RDP Client**

Connect

info

Connect to an instance using the browser-based client.

Instance ID

i-050d52934f9cd754c (EC2)

VPC ID

vpc-05d76c99d661a74f5

Security groups

sg-03cb52b6b1f7ef0b7 (launch-wizard-1)

IAM role

-

SSM Session Manager

RDP client

EC2 serial console

Record RDP connections

You can now record RDP connections using AWS Systems Manager just-in-time node access. [Learn more](#)

Try for free

X

Instance ID

i-050d52934f9cd754c (EC2)

Connection Type

Connect using RDP client

Download a file to use with your RDP client and retrieve your password.

Connect using Fleet Manager

To connect to the instance using Fleet Manager Remote Desktop, the SSM Agent must be installed and running on the instance. For more information, see [Working with SSM Agent](#)

You can connect to your Windows instance using a remote desktop client of your choice, and by downloading and running the RDP shortcut file below:

Download remote desktop file

Click **Get Password**

Password

Get password

If you've joined your instance to a directory, you can use your directory credentials to connect to your instance.

Cancel

Upload your downloaded .pem key file

Click **Decrypt Password**

Instance ID

i-050d52934f9cd754c (EC2)

Key pair associated with this instance

Devopskey

Private key

Either upload your private key file or copy and paste its contents into the field below.

Upload private key file

Devopskey.pem

1.67 KB

Private key contents

-----BEGIN RSA PRIVATE KEY-----  
MIIEowIBAAKCAQEApmHqoSq/IS40Ne5nqEpKjyrPObjx3wu6+jl7TD9izCwSzqUp  
Di+pGS+dkjrcWBvkJA/tcmjYt0SsbP73vGp/zPvT+GVDoBxk8Cz0CrbLU0VRG02a  
ACJXCTJN6uWBI6mE2V7kTLsnvPR36tdCplw4h2o88wLYYYaK8JvQ47SQdLV3tNYY  
7uOWWnQCgyg043/fubRERo3Ne5HJx6HOTawGD5D+eLfbYUbyDX7aDJWn2pIOWigD  
E9PlxhmlSwUQZGbnTJ3btSs6AzmnKBUdiim56M5tTXHhTrq6dykaeD3HjLmfdi2M  
F9qldwyv4NE8eExdNsaTNH9JjoSEUXs9eMvFQIDAQABoIBABnLTZZjinReNeDB  
d/oaPmTnYnA1k+bqbUz3mfruRCqFWIbHnqDT59oMf/iIOrguaQ8vMHsI0iikpoB

Cancel

Decrypt password

You will get:

Public DNS

ec2-100-31-119-81.compute-1.amazonaws.com

Password

8HEk%\$&n@DX;NpW1,jHe8t7kbjE.?Vg\*


Username

info

Administrator

### ◆ Step 3 — Connect Using RDP (From Your PC)

#### Open Remote Desktop




#### Enter Details

- **Computer: Public IPv4 Address (from EC2 instance)**
- **Username: Administrator**
- **Password: (decrypted password)**

#### Click Connect → Yes

✓ **Now Windows Server Desktop opens.**



## ◆ Step 5 — Open CMD in Windows VM

Inside EC2 Windows machine:

### ◆ Step 1 — Exit SConfig Menu

15


### ◆ Step 2 — Open Command Prompt (CMD)

Cmd

### ◆ Step 3 — Get About System Info (Required Output)

Systeminfo

Your output will be:



```
Administrator: C:\Windows\system32\cmd.exe - cmd
WARNING: To launch Server Configuration tool again, run "SConfig"

C:\Users\Administrator>cmd
Microsoft Windows [Version 10.0.20348.4773]
(c) Microsoft Corporation. All rights reserved.

C:\Users\Administrator>systeminfo

Host Name:                EC2AMAZ-932ILD1
OS Name:                   Microsoft Windows Server 2022 Datacenter
OS Version:                10.0.20348 N/A Build 20348
OS Manufacturer:          Microsoft Corporation
OS Configuration:          Standalone Server
OS Build Type:              Multiprocessor Free
Registered Owner:          EC2
Registered Organization:    Amazon.com
Product ID:                 00454-60000-00001-AA398
Original Install Date:      2/27/2026, 9:17:16 PM
System Boot Time:           2/28/2026, 12:53:30 PM
System Manufacturer:        Amazon EC2
System Model:               t3.micro
System Type:                x64-based PC
Processor(s):               1 Processor(s) Installed.
                           [01]: Intel64 Family 6 Model 85 Stepping 4 GenuineIntel ~2500 Mhz
BIOS Version:               Amazon EC2 1.0, 10/16/2017
Windows Directory:          C:\Windows
System Directory:            C:\Windows\system32
Boot Device:                 \Device\HarddiskVolume1
System Locale:                en-us;English (United States)
Input Locale:                en-us;English (United States)
```