GETTING STARTED CORTEX CODE CLI

© 2026 Snowflake Inc. All Rights Reserved

Agenda

1. Validate Cortex Code Access in Snowsight
2. Install Cortex Code CLI
3. Create Snowflake Connection Config
4. Test Run the Cortex Code CLI

© 2026 Snowflake Inc. All Rights Reserved

Validate Cortex Code in Snowsight





Access Cortex Code via Snowsight by clicking on the blue star in the bottom right corner in the UI

© 2026 Snowflake Inc. All Rights Reserved

Installing the CoCo CLI on Mac

INSTALL VIA TERMINAL

```
curl -LsS https://ai.snowflake.com/static/cc-scripts/install.sh | sh
```

Architectures

- x64 – Supported.
- ARM64 – Supported

VERIFY INSTALL

```
cortex --version
```

During Installation

- When prompted to add cortex to your PATH, respond with y.
- If the cortex command is not recognized after installation:
- Close and reopen your terminal, or
- Restart your machine to ensure PATH changes take effect.

© 2026 Snowflake Inc. All Rights Reserved

Installing the CoCo CLI on Mac

CONFIGURE SNOWFLAKE CONNECTIONS

- Cortex Code uses the same connection files as SnowCLI, under your home directory. On Macs that's typically:
- ~/.snowflake/config.toml (or connections.toml if you already use that).
- Minimal example (adapt to your accounts/roles):

```
default_connection_name = "DEMO"  # NAME FOR DEFAULT SNOWFLAKE CONNECTION
[connections.DEMO]  # NAME FOR SNOWFLAKE CONNECTION (SAME AS ABOVE IF DEFAULT)
account   = "<YOUR_DEMO_ACCOUNT>"      # e.g. ACCOUNT IDENTIFIER
user      = "<YOUR_DEMO_USERNAME>"     # e.g. AUTHENTICATION VARIABLE
password  = "<YOUR_DEMO_PAT>"
role      = "<YOUR_DEMO_ROLE>"         # e.g. NEED A ROLE FOR CONNECTION
warehouse = "<YOUR_DEMO_WAREHOUSE>"
```

LAUNCH CORTEX CODE CLI USING YOUR SQL CONNECTION

```
cortex -c DEMO # connect to connection name
```

© 2026 Snowflake Inc. All Rights Reserved

Installing the CoCo CLI on Windows

INSTALL VIA POWERSHELL

```
irm https://ai.snowflake.com/static/cc-scripts/install.ps1 | iex
```

Architectures

- x64 – Supported.
- ARM64 – Support is in progress. Current builds may rely on experimental runtime support and are not yet recommended for production use.

VERIFY INSTALL

```
cortex --version
```

During Installation

- When prompted to add cortex to your PATH, respond with y.
- If the cortex command is not recognized after installation:
  - Close and reopen your terminal, or
  - Restart your machine to ensure PATH changes take effect.

© 2026 Snowflake Inc. All Rights Reserved

Installing the CoCo CLI on Windows

CONFIGURE SNOWFLAKE CONNECTIONS

- Cortex Code uses the same connection files as SnowCLI, under your home directory. On Windows that's typically:
- %USERPROFILE%.snowflake\config.toml (or connections.toml if you already use that).
- Minimal example (adapt to your accounts/roles):

```
default_connection_name = "DEMO"  # NAME FOR DEFAULT SNOWFLAKE CONNECTION
[connections.DEMO]  # NAME FOR SNOWFLAKE CONNECTION (SAME AS ABOVE IF DEFAULT)
account   = "<YOUR_DEMO_ACCOUNT>"      # e.g. ACCOUNT IDENTIFIER
user      = "<YOUR_DEMO_USERNAME>"     # e.g. AUTHENTICATION VARIABLE
password  = "<YOUR_DEMO_PAT>"
role      = "<YOUR_DEMO_ROLE>"         # e.g. NEED A ROLE FOR CONNECTION
warehouse = "<YOUR_DEMO_WAREHOUSE>"
```

LAUNCH CORTEX CODE CLI USING YOUR SQL CONNECTION

```
cortex -c DEMO # connect to connection name
```

© 2026 Snowflake Inc. All Rights Reserved

Creating a Snowflake Connections Config

ON MAC

Run this code in your terminal to create the connections config file

```
mkdir -p ~/.snowflake
touch ~/.snowflake/config.toml
chmod 600 ~/.snowflake/config.toml
```

Then run this command to open the file to edit and add in config

```
open -e ~/.snowflake/config.toml
```

ON WINDOWS

Run this code in powershell to create the connection config file

```
mkdir $env:USERPROFILE\.snowflake -Force
New-Item -ItemType File -Path $env:USERPROFILE\.snowflake\config.toml
-Force
```

Then run this command to open the file to edit and add in config

```
notepad $env:USERPROFILE\.snowflake\config.toml
```

Filling out the Default Connection

LOG IN AND FIND SETTING INFORMATION



CLICK ON CONNECTION AND FIND DEFAULTS



© 2026 Snowflake Inc. All Rights Reserved

Ways to Authenticate Connections

CREATE AND AUTHENTICATE A CONNECTION TO SNOWFLAKE

There are many ways to create a connection to Snowflake. These are included into your connection configuration as credentials to identify you as logging into your connection. Here are some examples of environment variables used in Snowflake credentials:

- `SNOWFLAKE_ACCOUNT`
- `SNOWFLAKE_USER`
- `SNOWFLAKE_PASSWORD`
- `SNOWFLAKE_TOKEN`
- `SNOWFLAKE_TOKEN_FILE_PATH`
- `SNOWFLAKE_OAUTH_CLIENT_ID`
- `. . .`

Find more examples and walk through creating your connection parameter in the [Manage Snowflake connections guide](#).

© 2026 Snowflake Inc. All Rights Reserved

Launching Cortex Code

LAUNCH CORTEX CODE CLI USING YOUR SQL CONNECTION

```
cortex -c DEMO # connect to connection name
```

- After connecting to cortex code (using the connect -c command and your connection name (in this example, DEMO), you will see the Cortex Code CLI interface
- From here is where we will cover more advanced usages of Cortex Code in our session, but we can test the connection first by asking a simple question:



© 2026 Snowflake Inc. All Rights Reserved