For Linux:-

```
Last sector, +/-sectors or +/-size{K,M,G,T,P} (2048-25165823, default 25165823): +4G

Created a new partition 1 of type 'Linux' and of size 4 GiB.

Command (m for help): w
The partition table has been altered.
Calling ioctl() to re-read partition table.
Syncing disks.

ubuntu@ip-172-31-47-195:~$ lsblk
NAME         MAJ:MIN RM  SIZE RO TYPE MOUNTPOINTS
loop0          7:0    0 27.6M  1 loop /snap/amazon-ssm-agent/11797
loop1          7:1    0   74M  1 loop /snap/core22/2163
loop2          7:2    0 50.9M  1 loop /snap/snapd/25577
nvme0n1      259:0    0    8G  0 disk
├─nvme0n1p1  259:1    0    7G  0 part /
├─nvme0n1p14 259:2    0    4M  0 part
├─nvme0n1p15 259:3    0  106M  0 part /boot/efi
└─nvme0n1p16 259:4    0  913M  0 part /boot
nvme1n1      259:5    0   12G  0 disk
└─nvme1n1p1  259:6    0    4G  0 part
ubuntu@ip-172-31-47-195:~$ sudo mkfs.ext4 /dev/nvme1n1
mke2fs 1.47.0 (5-Feb-2023)
Found a dos partition table in /dev/nvme1n1
Proceed anyway? (y,N) y
Creating filesystem with 3145728 4k blocks and 786432 inodes
Filesystem UUID: 0e02f08e-2abe-4a21-8668-c9ba2a70b936
Superblock backups stored on blocks:
        32768, 98304, 163840, 229376, 294912, 819200, 884736, 1605632, 2654208

Allocating group tables: done
Writing inode tables: done
Creating journal (16384 blocks): done
Writing superblocks and filesystem accounting information: done

ubuntu@ip-172-31-47-195:~$ sudo mkdir /mnt/myvol
ubuntu@ip-172-31-47-195:~$ sudo mount /dev/nvme1n1 /mnt/myvol
ubuntu@ip-172-31-47-195:~$ cd /mnt/myvol
ubuntu@ip-172-31-47-195:/mnt/myvol$ sudo touch a.txt
```

For Windows:-


ec2-13-60-166-221.eu-north-1.compute.amazona...
Hostname: EC2AMAZ-DRA4H2E
Instance ID: i-0708eb5494fa01e90
Private IPv4 address: 172.31.41.123
Public IPv4 address: 13.60.166.221
IPv6 address:
Instance size: c7i-flex.large
Availability Zone: eu-north-1b
Architecture: AMD64


Computer Management
File Action View Help
ec2-13-60-166-221.eu-north-1.compute.amazona...
Computer Management (Local)
System Tools
Task Scheduler
Event Viewer
Shared Folders
Local Users and Groups
Performance
Device Manager
Storage
Windows Server Backup
Disk Management
Services and Applications
Volume | Layout | Type | File System | Status | Capacity | Free Space | % Free
(Disk 0 partition 2) | Simple | Basic | | Healthy (EFI System Partition) | 500 MB | 500 MB | 100 %
New Volume (D:) | Simple | Basic | NTFS | Healthy (Basic Data Partition) | 4.88 GB | 4.86 GB | 100 %
Windows (C:) | Simple | Basic | NTFS | Healthy (Boot, Page File, Crash Dump, Basic Data Partition) | 29.50 GB | 10.67 GB | 36 %
Actions
Disk Management
More Actions
Disk 0
Basic
29.98 GB
Online
500 MB
Healthy (EFI System Partition)
Windows (C:)
29.50 GB NTFS
Healthy (Boot, Page File, Crash Dump, Basic Data Partition)
Disk 1
Basic
14.98 GB
Online
New Volume (D:)
4.88 GB NTFS
Healthy (Basic Data Partition)
10.10 GB
Unallocated