12.8 Lab: Secure a Home Wireless Network

Candidate: COMPTIA COMPTIA ()
Time Spent: 00:08

Score: 0%		
Task Summary		
Required Actions		

- × Change the Wireless Network Name (SSID) to PoliceVan
- X Configure the wireless security settings Show Details
- × Change the wireless access point's default administrator authentication credentials Show Details

Explanation 60

Complete this lab as follows:

- 1. Access, and sign into, the TPLink-AC1750 wireless access point.
 - a. In the URL field of Google Chrome, enter 192.168.0.254 and press Enter.
 - b. Maximize Google Chrome for easier viewing.
 - c. From the top menu bar, select the Wireless tab.
 - d. Enter the sign-in credentials:
 - Username: adminPassword: password
 - e. Select Sign In.
- 2. Change the Wireless Network Name (SSID) to PoliceVan.
 - a. Make sure the Wireless submenu of **Basic Settings** is selected.
 - b. Under Wireless Interface wlan0, change the Wireless Network Name (SSID) to PoliceVan.
 - c. Scroll down and select Apply Settings.
- 3. Configure the wireless security settings.
 - a. From the submenu bar, select the Wireless Security tab.
 - b. For Wireless Mode, use the drop-down list to select WPA.
 - c. Under Network Authentication, select WPA2 Personal.
 - d. Under WPA Algorithms, select CCMP-128 AES.
 - e. In the WPA Shared Key field, enter 4WatchingU.
 - f. (Optional) Select **Unmask** to verify your new shared key.
 - g. Scroll to the bottom and select Apply Settings.
- 4. Change the wireless access point's administration authentication credentials.
 - a. From the top menu bar, select the **Administration** tab.

- b. Make sure the **Management** submenu is selected.
- c. Change the Router Password settings as follows:
 - Router Username: @dm1n (1 is the number 1)
 - Router Password: **StayOut!** (O is the capital letter O).
 - Re-enter to confirm: **StayOut!** (O is the capital letter O).
- d. Scroll to the bottom and select Apply Settings.
- e. Select Save.
- f. Select **Reboot Router**.
- g. When prompted, select **Continue**.
- 5. Configure the laptop to connect to the wireless network and save the wireless profile settings.
 - a. From the top left, select Computer Desk.
 - b. On the Home-Laptop monitor, select Click to view Windows 11.
 - c. From the Notification area of the taskbar, select the **Network** icon.
 - d. To the right of the wireless icon, select the > icon.
 - e. Select the **PoliceVan** wireless network.
 - f. Make sure **Connect automatically** is selected.
 - g. Select **Connect**.
 - h. Enter 4WatchingU (the passphrase/network security key).
 - i. Select **Next**.
 - j. From the Notification area of the taskbar, right-click the *network* icon and select **Network & Internet settings** to confirm the connection.