

```

DRAWGBK(1, RGB(0, 0, 0)),layer7;
{=====}
MID := MA(CLOSE,26),DRAWNULL,COLORWHITE;
partline(MID, 1, RGB(0, 66, 99)),LAYER5,LINETHICK1;
{=====}
{*****}

{=====}
{===== 系统ZKQK =====}
{=====}
{----- QK -----}
QK := SMA(C,3,1);
QD := SMA(QK,3,1);
QJ := 3*QK-2*QD;
{----- ZK -----}
ZK := SMA(C,7,1);
ZD := SMA(ZK,3,1);
ZJ := 3*ZK-2*ZD;
ZH := 5*ZK-4*ZD;
{----- 划线 -----}
partline(ZK, 1, RGB(0, 0, 40)),LAYER6,LINETHICK4;
partline((ZK+ZD)/2,1, RGB(0, 0, 50)),LAYER6,LINETHICK2;
partline(ZD, 1, RGB(0, 0, 60)),LAYER6,LINETHICK1;
{-----}
partline(QK, 1, RGB(80, 100, 100)),LAYER4;
partline(ZH, 1, RGB(30, 0, 0)),LAYER5,LINETHICK2;
partline(QJ, 1, RGB(30, 0, 0)),LAYER5;
{----- 立柱 -----}
STICKLINE( QK>=ZK, ZK, QK, 4, 0),COLOR22227B,LAYER7;
STICKLINE( QK< ZK, ZK, QK, 4, 0),COLOR005B22,LAYER7;
{----- 信号 -----}
{
DRAWICON(cross(QK,ZK), ZD,12), ALIGN1,VALIGN0,LAYER6,COLORRED;
DRAWICON(cross(ZK,QK), ZD,13), ALIGN1,VALIGN2,LAYER6,COLORGREEN;
}
{=====}
{*****}

{=====}
{===== 系统FQK =====}
{=====}
{----- FQK -----}
FA := EMA(QK,3);
FB := EMA(EMA(EMA(EMA(CLOSE,3),3),3),3);

```

```

{----- 划线 -----}
PARTLINE(FA, 1, RGB(0, 222, 0)),LAYER2,linethick1;
PARTLINE(FB, 1, RGB(205, 149, 12)),LAYER4,linethick2;
{----- 信号 -----}
DRAWICON(cross(FA,FB), FB,12), ALIGN1,VALIGN0,LAYER6,COLORRED;
DRAWICON(cross(FB,FA), FB,13), ALIGN1,VALIGN2,LAYER6,COLORGREEN;
{=====}
{*****}

```

```

{=====}
{===== 乾坤阴阳 =====}
{=====}
IFS(FA >= FB, '阳', ''), DRAWNULL, COLORred;
IFS(FA < FB, '阴', ''), DRAWNULL, COLORgray;

IFS(FA - FB >= ref(FA - FB,1) , '增','减'), DRAWNULL, COLORwhite;

{=====}
{=====}
IFS(QJ>ZH AND (FA< FB) AND QK<=ZK, '玄龙试仓', ''), DRAWNULL, COLORAAAA66;
IFS(QJ>ZH AND (FA>=FB) AND QK<=ZK, '青龙建仓', ''), DRAWNULL, COLORCYAN;
{-----}
IFS(QJ>ZH AND (FA>=FB) AND QK>ZK, '朱雀飞升', ''), DRAWNULL, COLORRED;
{-----}
IFS(QJ<=ZH AND (FA>=FB) AND QK>ZK, '白虎减仓', ''), DRAWNULL, COLORWHITE;
IFS(QJ<=ZH AND (FA< FB) AND QK>ZK, '玄武清仓', ''), DRAWNULL, COLORGRAY;
{增加FA方向的判断，确定二次飞升}
{-----}
IFS(QJ<=ZH AND (FA< FB) AND QK<ZK, '玄武勿动', ''), DRAWNULL, COLORGRAY;
{=====}
{*****}

```

```

{=====}
{===== 赋值 =====}
{=====}
C,DRAWNULL, COLORwhite;
{=====}

{=====}

```

```

bH: 100*(C-ZH)/ZH,DRAWNULL,COLORAAAAAA;
bC: 100*(C-QK)/QK,DRAWNULL,COLORAAAAAA;
bM: 100*(C-MID)/MID,DRAWNULL,COLORAAAAAA;
{----- QJ-ZH -----}
QJZH : 100*(QJ - ZH)/MAX(C,1)
,DRAWNULL,COLORYELLOW;

FAFB : 100*(FA - FB)/MAX(C,1)
,DRAWNULL,COLORYELLOW;

QKZK : 100*(QK - ZK)/MAX(C,1)
,DRAWNULL,COLORYELLOW;
{=====}
{
龙 : FA>=FB AND QK<=ZK, DRAWNULL, COLORCYAN;
雀 : FA>=FB AND QK>ZK, DRAWNULL, COLORRED;
虎 : FA<FB AND QK>ZK, DRAWNULL, COLORWHITE;
武 : FA<FB AND QK<=ZK, DRAWNULL, COLORGRAY;
}
{=====}
{*****}
{*****}

{=====}
{===== 选股专用 =====}
{=====}
{=====}
选阳初 : QJ>ZH AND QK>ZK
AND (REF(QJZH,1)>0 AND REF(QKZK,1)>0)=0
,DRAWNULL,COLORRED;
{STICKLINE(阳一, OPEN,CLOSE, 6,0),COLOR008BEE,LAYER7;}

选阳三 : count(cross(QK,ZK),3)=1 and C>=QK, DRAWNULL,COLORRED;
{STICKLINE(阳一, OPEN,CLOSE, 6,0),COLOR008BEE,LAYER7;}
{=====}

{以下乾坤与选天机等合并}
{----- ZXX:地机 -----}
选地机 :=
(
(QJ>ZH AND QK<=ZK)
AND QJ>=QK
)
AND QJ>REF(QJ,1)
, COLORAAAA00,DRAWNULL;
{STICKLINE(选地机, OPEN,CLOSE, 6,0),COLORAAAA00,LAYER6;}

{----- ZXX:天机 -----}

```

选天机：

```
(  
(QJ>ZH AND QK<=ZK)  
AND QJ>=QK  
)  
AND QJ>REF(QJ,1)  
AND QJ>ZK  
AND C>ZK  
, COLORCYAN,DRAWNULL;
```

```
{STICKLINE(选天机, OPEN,CLOSE, 6,0),COLORCYAN,LAYER6;}
```

```
{=====}
```

```
{=====}
```

鼎：

```
(QJ>ZH AND QK>ZK)  
AND OPEN<QK AND C>QK  
AND C>ZH*0.97  
,DRAWNULL,COLORRED;
```

```
{=====}
```

```
{*****}
```