


COMPUTER NETWORKS

WEEK-5

LAB OBSERVATION

Shashank M S – 1BM21CS201



1. Create a topology for DNS:




2.

The screenshot shows a software interface for managing network services. The top navigation bar includes tabs for Physical, Config, Services, Desktop, and Custom Interface. The Services tab is selected, revealing a sidebar with options like HTTP, DHCP, DHCPv6, TFTP, DNS, SYSLOG, AAA, NTP, EMAIL, and FTP. The main pane is titled 'DNS' and contains settings for the 'DNS Service' (radio button set to 'On') and a table for 'Resource Records'. A new record is being added, with the 'Name' field set to 'www.cnlab.com', 'Type' set to 'A Record', and 'Address' set to '10.0.0.2'. Below this, a table lists existing records: No. 0, Name www.cnlab.com, Type A Record, Detail 10.0.0.2.

No.	Name	Type	Detail
0	www.cnlab.com	A Record	10.0.0.2



3. Configure DHCP within LAN:



IBM21CS218

Router0 10.0.0.1

Physical Config CLI

IOS Command Line Interface

```
4 FastEthernet/IEEE 802.3 interface(s)
2 Low-speed serial(sync/async) network interface(s)
32K bytes of non-volatile configuration memory.
63488K bytes of ATA CompactFlash (Read/Write)

--- System Configuration Dialog ---

Continue with configuration dialog? [yes/no]: no

Press RETURN to get started!

Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface FastEthernet0/0
Router(config-if)#ip address 10.0.0.1 255.0.0.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#exit
Router(config)#

Copy Paste
```

1BM21CS218

Server1 10.0.0.2

Physical Config Services Desktop Custom Interface

SERVICES

- HTTP
- DHCP
- DHCPv6
- TFTP
- DNS
- SYSLOG
- AAA
- NTP
- EMAIL
- FTP

DHCP

Interface: FastEthernet0 Service: On Off

Pool Name: serverPool
Default Gateway: 0.0.0.0
DNS Server: 0.0.0.0
Start IP Address : 10 0 0 0
Subnet Mask: 255 0 0 0
Maximum number of Users : 512
TFTP Server: 0.0.0.0

Add Save Remove

Pool Name	Default Gateway	DNS Server	Start IP Address	Subnet Mask	Max User	TFTP
server...	10.0.0.1	10.0.0.2	10.0.0.1	255.0.0.0	512	10.0.0.2
server...	0.0.0.0	0.0.0.0	10.0.0.0	255.0.0.0	512	0.0.0.0

PC1

Physical Config Desktop Custom Interface

IP Configuration

IP Configuration

DHCP Static

IP Address: 10.0.0.3
Subnet Mask: 255.0.0.0
Default Gateway: 0.0.0.0
DNS Server:

IPv6 Configuration

DHCP Auto Config Static

IPv6 Address: /
Link Local Address: FE80::260:47FF:FEA7:2D9B
IPv6 Gateway:
IPv6 DNS Server:

