

**LAPORAN PRAKTIKUM**  
**INTERNET OF THINGS II**

Modul 3: Jaringan Nirkabel dan Komunikasi HTTP



Disusun Oleh:

Shavina Naura Putri

25782055

Dosen Pengampu:

Dr. Ir. Septafiansyah Dwi Putra, S.T., M.T.

Agus Ambarwari, S.Pd., M.Kom.

Andi Saptono, S.Kom


**TEKNOLOGI REKAYASA INTERNET**  
**JURUSAN TEKNOLOGI INFORMASI**  
**POLITEKNIK NEGERI LAMPUNG**

**2026**

## LATIHAN 3.7

### 3.7 Tugas: Pengembangan *Web Server* Cerdas dan Analisis Arsitektur

#### CLIENT



```
Blink | Arduino IDE 2.3.10
File Edit Sketch Tools Help
NodeMCU 1.0 (ESP-12E...)
Blinkino
1 #include <ESP8266WiFi.h>
2 #include <ESP8266HTTPClient.h>
3 #include <WiFiClient.h>
4
5 const char* ssid = "terminator";
6 const char* password = "jereyml777";
7
8 // Alamat IP Web Server Target
9 const char* serverName = "http://18.33.148.16/relay/on";
10 const byte ldrPin = A8;
11
12 void setup() {
13   Serial.begin(115200);
14   WiFi.mode(WIFI_STA);
15   WiFi.begin(ssid, password);
16
17   while (WiFi.status() != WL_CONNECTED) {
18     delay(500);
19     Serial.print(".");
20   }
21   Serial.println("\nClient Terhubung ke Wi-Fi!");
22 }
23
24 void loop() {
25   int ldrValue = analogRead(ldrPin);
26
27   // Jika kondisi intensitas cahaya melampaui batas (> 300)
28   if (WiFi.status() == WL_CONNECTED) {
29     if (ldrValue > 300) {
30       HTTPClient http;
31       http.begin(serverName);
32       http.GET();
33       Serial.print("HTTP Response code: ");
34       Serial.println(http.getStatusCode());
35     }
36   }
37 }
```

Output Serial Monitor X

Message (Enter to send message to 'NodeMCU 1.0 (ESP-12E Module)' on COM3)

```
15:10:12.071 -> Batas Terlampau! HTTP Response code: -1
15:10:24.457 -> Batas Terlampau! HTTP Response code: 200
15:10:36.507 -> Batas Terlampau! HTTP Response code: 200
15:10:48.690 -> Batas Terlampau! HTTP Response code: 200
15:14:00.478 -> Batas Terlampau! HTTP Response code: 200
15:14:12.756 -> Batas Terlampau! HTTP Response code: 200
15:14:24.872 -> Batas Terlampau! HTTP Response code: 200
15:14:36.891 -> Batas Terlampau! HTTP Response code: 200
15:14:49.030 -> Batas Terlampau! HTTP Response code: 200
15:15:01.109 -> Batas Terlampau! HTTP Response code: 200
15:15:13.202 -> Batas Terlampau! HTTP Response code: 200
15:15:25.272 -> Batas Terlampau! HTTP Response code: 200
15:15:37.349 -> Batas Terlampau! HTTP Response code: 200
15:15:49.408 -> Batas Terlampau! HTTP Response code: 200
```

#### SERVER

