

Module 3 – Guided Lab: Hosting a Static Website




ACL enabled

| sure d its plica | ccess is granted to buckets and objects through access control lists (ACLs), bucket policies, access point policies, or all. In order to chat public access to this bucket and its objects is blocked, turn on Block all public access. These settings apply only to this bucket access points. AWS recommends that you turn on Block all public access, but before applying any of these settings, ensure that your cions will work correctly without public access. If you require some level of public access to this bucket or objects within, you can zee the individual settings below to suit your specific storage use cases. Learn more |
|------------------------|--|
| | bock all public access ning this setting on is the same as turning on all four settings below. Each of the following settings are independent of one another. Block public access to buckets and objects granted through new access control lists (ACLs) S3 will block public access permissions applied to newly added buckets or objects, and prevent the creation of new public access ACLs for existing buckets and objects. This setting doesn't change any existing permissions that allow public access to S3 resources using ACLs. |
| - 🗌 | Block public access to buckets and objects granted through <i>any</i> access control lists (ACLs) S3 will ignore all ACLs that grant public access to buckets and objects. |
| - 🗆 | Block public access to buckets and objects granted through <i>new</i> public bucket or access point policies S3 will block new bucket and access point policies that grant public access to buckets and objects. This setting doesn't change any existing policies that allow public access to S3 resources. |
| - 🗆 | Block public and cross-account access to buckets and objects through <i>any</i> public bucket or access point policies S3 will ignore public and cross-account access for buckets or access points with policies that grant public access to buckets and objects. |


Then create bucket



Go to properties



In properties tab




Edit static website hosting Static website hosting Use this bucket to host a website or redirect requests. Learn more ☑ Static website hosting Disable Enable Hosting type Host a static website Use the bucket endpoint as the web address. Learn more ☑

Write Index.html, error.html

Redirect requests for an object

Redirect requests to another bucket or domain. Learn more 🔀



But didn't work yet




403 Forbidden


- Code: AccessDenied
- Message: Access Denied
- RequestId: TDFS32DFWXK6BQSB
- HostId: 8AsOuINkfnG8njm6yNXb9VXWhzF/apsCbjMa+z3K1ph/tON3njNY2lCgHw45mCKEuxpS34IL7eo=

An Error Occurred While Attempting to Retrieve a Custom Error Document

- Code: AccessDenied
- Message: Access Denied

Upload files







CREATED BY NWENWE