

FactoryTalk ProductionCentre培训

基础介绍 – User Access

ISPB (信息软件部门) 2016年9月18日







课程说明

- 课程名字:

FTPC基本培训 – User Access

- 课程描述:

本课程介绍FactoryTalk ProductionCentre的用户权限配置

目标受众:

业务用户,项目经理,开发人员

- 培训目标:完成该课程之后,学员将能够
 - 了解用户权限控制、配置



课程说明

- 课堂纪律:
 - 关闭手机铃声,设置为静音模式
 - 举手提问、发言



内容

Rockwell Automation


User Access介绍

User Access配置

QA


Rockwell Automation

- User **用户对象**
- □ 设置用户名、描述信息
- □ 设定用户密码
- □ 设定密码有效期
- □ 设定用户账号状态
- □ 设定用户账号失效日期
- □ 关联用户默认页面
- □ 关联用户默认班次
- □ 关联用户组




User Access介绍

- User Group 用户组对象
- □ 设置用户组名、描述信息
- □ 关联用户
- □ 关联班次
- □ 5个默认用户组
 - PlantOpsAdmin
 - PlantOpsDesigner
 - PlantOpsSupervisor
 - PlantOpsOperator
 - PlantOpsGuest



Rockwell Automation

- Access Privilege 访问权限
- □ 设定Performers用户组
- □ 设定Second Signers (Option)用户组
- 兼容JAAS (Java验证与授权API)
 - GuestPrivilege
 - OperatorPrivilege
 - SupervisorPrivilege
 - DesignerPrivilege
 - AdminPrivilege
 - PlantOpsNotRequiredPrivilege



Rockwell Automation

- Access Privilege 访问权限(续)
- □ FSMConfigurationDesigner: 允许用户保存FSM变更。是建立Java类和FSM关联关系必须的权限
- □ OpenCloseForm: 允许用户在Shop Operations中打开或关闭页面
- PDCreate: 允许用户在Process Designer中创建或保存对象.
- □ PDDelete: 允许用户在Process Designer中删除对象.
- □ PDUDADesigner: 允许用户在Process Designer中更改UDADefinition对象
- PDUpdate: 允许用户在Process Designer中更改或保存对象
- ProcessDesigner: 允许用户登录Process Designer
- □ ProcessModeler: 允许用户登录Process Designer 但是访问不了forms, subroutines, 或event sheets对象
- □ RuntimeOptions: 允许用户在Shop Operations修改站点、区域,或禁用自动超时和时间脚本
- □ ShopOperations:允许用户执行操作员事务
- □ UserAuthentication:允许用户在登录Shop Operations Server 调用中间件方法来验证用户身份
- □ VersioningPlatformDesigner: 允许用户启用、配置或禁用版本平台特性

Access Privilege 访问权限(续)

Access Privileges	User Group				
	PlantOpsAdmin	PlantOpsDesigner	PlantOpsSupervisor	PlantOpsOperator	PlantOpsGuest
FSMConfigurationDesigner	х	X			
OpenCloseForm	x	X	×		
PDCreate	x	×			
PDDelete	x	×			
PDUDADesigner	X	×			
PDUpdate	x	×			
ProcessDesigner	х	X			
ProcessModeler	x	X			
RuntimeOptions	X	×	×		
ShopOperations	x	×	×	x	
UserAuthentication	x	×	X	х	×
VersioningPlatformDesigner	x	X			
Backward Support Access Privileg	ges				
GuestPrivilege	x	×	×	X	×
OperatorPrivilege	х	×	×	x	
SupervisorPrivilege	x	×	×		
DesignerPrivilege	х	X			
AdminPrivilege	×				
	ne system will not perform aut	horization for this privilege. Use it on a	method that does not require any authorization.		

内容

Rockwell Automation


User Access介绍

User Access配置

QA


User Access晒置

- 创建用户




User Access晒置

• 创建用户组



User Access配置

- 创建用户组



User Access API



- 用户权限判断

User.hasPrivilege(AccessPrivilege accessPrivilege)

事务操作中指定权限控制:

Part.changeVersioningState(Time trxTime, java.lang.String stateName, java.lang.String comment, AccessPrivilege accessPrivilege)

内容

Rockwell Automation

User Access介绍

User Access配置

QA













Allen-Bradley • Rockwell Software



www.rockwellautomationteched.com

Copyright © 2016 Rockwell Automation, Inc. All Rights Reserved