

PSD2Outbound GCO Alert-Node Restart Detected

PSD2Outbound GCO Alert-Node Restart Detected

Why do we have this alert?

- To notify if any issues with the k8s node

What does this alert mean?

This check is designed to indicate that a node is not ready to accept pods.

Impact to customer-

- It will affect the processing and incoming requests.

Investigation Steps-

- The NodeNotReady error in GCO logs for Kubernetes (K8) nodes typically indicates that a node is not ready to accept pods. This can occur due to various reasons such as:

Node is still initializing or rebooting

Node is experiencing network connectivity issues

Node is running low on resources (e.g., CPU, memory, or disk space)

- **Check node status:**

Inside the Navigation Menu > Click or hover over the "Kubernetes Engine".

Then click on the "Cluster" you can see one cluster "outbound-prd-gke" open it. Select Node tab and check the status.

- **Verify node logs:**

Click on the Node to access its details

Navigate to the Logs tab. Apply a filter to display only logs with severity levels of **Alert**, **Critical**, or **Error**.

- **Check system resources:** Verify that the node has sufficient resources (CPU, memory, disk space) to operate correctly.

If not able to identify/resolve the issue, you may want to investigate further or seek additional help from Dev team and can reach out to Google Cloud support as well. [Cases – Support – db-prd-mp-psd2ce-obd – Google Cloud console](#)

Verification Steps-

Check the node status- Inside the Navigation Menu --> "Kubernetes Engine"--> Cluster "outbound-prd-gke" -->Node tab and check the status.

- Check the node status- Inside the Navigation Menu --> "Kubernetes Engine"--> Cluster "outbound-prd-gke" -->Node tab and check the status.
- Verification steps after a node restart is very crucial.
- check and confirm node have restarted and verify its current uptime.
- Monitor CPU, memory and disk usage to ensure they are within normal limits.
- Confirm that all critical services in running status.
- Examine the main application and service logs for any recent ERROR,FATAL or CRITICAL message during startup phase.
- Check for indicating a successful initialization and confirm the node is ready or Up.

Additional Information-

Contact list - [Contact List](#)

