Windows PowerShell Help System

23 March 2026
00:38

Help System Powershell

The Get-Help cmdlet in PowerShell is a fundamental tool used to access **built-in documentation, examples, and syntax for commands and concepts directly within the console**. It is essential for learning and effectively utilizing the extensive capabilities of the PowerShell environment

To use help system of powershell
Get-help get-service

```
PS C:\Users\lenovo> get-help get-service

NAME
    Get-Service

SYNTAX
    Get-Service [[-Name] <string[]>] [-ComputerName <string[]>] [-DependentServices] [-RequiredServices] [-Include
    <string[]>] [-Exclude <string[]>]  [<CommonParameters>]

    Get-Service -DisplayName <string[]> [-ComputerName <string[]>] [-DependentServices] [-RequiredServices] [-Include
    <string[]>] [-Exclude <string[]>]  [<CommonParameters>]

    Get-Service [-ComputerName <string[]>] [-DependentServices] [-RequiredServices] [-Include <string[]>] [-Exclude
    <string[]>] [-InputObject <ServiceController[]>]  [<CommonParameters>]


ALIASES
    gsv


REMARKS
    Get-Help cannot find the Help files for this cmdlet on this computer. It is displaying only partial help.
        -- To download and install Help files for the module that includes this cmdlet, use Update-Help.
        -- To view the Help topic for this cmdlet online, type: "Get-Help Get-Service -Online" or
           go to https://go.microsoft.com/fwlink/?LinkID=113332.
```

To check the detailed services in the get-service command
Get-help get-service -detailed

```
PS C:\Users\lenovo> get-help get-service -Detaile

NAME
    Get-Service

SYNTAX
    Get-Service [[-Name] <string[]>] [-ComputerNa
    <string[]>] [-Exclude <string[]>]  [<CommonPa

    Get-Service -DisplayName <string[]> [-Compute
    <string[]>] [-Exclude <string[]>]  [<CommonPa

    Get-Service [-ComputerName <string[]>] [-Depe
    <string[]>] [-InputObject <ServiceController[


PARAMETERS
    -ComputerName <string[]>

    -DependentServices
```

To check the all important info developed used like names , syntax, descriptions etc
Get-help get-service -full

```
PS C:\Users\lenovo> get-help get-service -Full

NAME
    Get-Service

SYNTAX
    Get-Service [[-Name] <string[]>] [-ComputerName <string[]>] [-DependentServices] [-RequiredServices] [-Include
    <string[]>] [-Exclude <string[]>]  [<CommonParameters>]

    Get-Service -DisplayName <string[]> [-ComputerName <string[]>] [-DependentServices] [-RequiredServices] [-Include
    <string[]>] [-Exclude <string[]>]  [<CommonParameters>]

    Get-Service [-ComputerName <string[]>] [-DependentServices] [-RequiredServices] [-Include <string[]>] [-Exclude
    <string[]>] [-InputObject <ServiceController[]>]  [<CommonParameters>]


PARAMETERS
    -ComputerName <string[]>

        Required?                    false
        Position?                    Named
        Accept pipeline input?       true (ByPropertyName)
        Parameter set name           (All)
        Aliases                      Cn
        Dynamic?                     false

    -DependentServices

        Required?                    false
        Position?                    Named
        Accept pipeline input?       false
        Parameter set name           (All)
        Aliases                      DS
        Dynamic?                     false

    -DisplayName <string[]>

        Required?                    true
        Position?                    Named
        Accept pipeline input?       false
        Parameter set name           DisplayName
        Aliases                      None
        Dynamic?                     false

    -Exclude <string[]>
```

Get-help get-service -Online

```
S C:\Users\lenovo> get-help get-service -online
S C:\Users\lenovo>
```

The Microsoft edge opens

```
S C:\Users\lenovo>
```

The Microsoft edge opens



Parameter Specific Help

To get the info of a specific parameter such as name the command used is
Get-help get-service -Parameter DisplayName

```
PS C:\Users\lenovo> get-help get-service -Parameter DisplayName

-DisplayName <string[]>

    Required?                    true
    Position?                    Named
    Accept pipeline input?       false
    Parameter set name           DisplayName
    Aliases                      None
    Dynamic?                     false
```

To view the output in separate window

Get-help get-service -ShowWindow
Get-help set-storagesetting -showwindow



To Update Help Files

Update-help : This command is used to update the all files automatically.
To update a specific module - **update-help -Module** : require internet

If we want to update the files on the machine where the internet access is not there

1. Download these help files on machine having internet
2. Copy it in pen drive and then run on different machine
   To do soo,

Save-help -Module Storage -Destination C:\Documents : it is used to download 2 files(cabinet, html files) on system in document folder
Update-help -module Storage C:\Documents -Module Storage : run this command
Import-Module Storage

Get-command -Module Storage

```
PS C:\Users\lenovo> Get-command -Module Storage

CommandType     Name                                               Version    Source
-----------     ----                                               -------    ------
Alias           Disable-PhysicalDiskIndication                     2.0.0.0    Storage
Alias           Disable-StorageDiagnosticLog                       2.0.0.0    Storage
Alias           Enable-PhysicalDiskIndication                      2.0.0.0    Storage
Alias           Enable-StorageDiagnosticLog                        2.0.0.0    Storage
Alias           Flush-Volume                                       2.0.0.0    Storage
Alias           Get-DiskSNV                                        2.0.0.0    Storage
Alias           Get-PhysicalDiskSNV                                2.0.0.0    Storage
Alias           Get-StorageEnclosureSNV                            2.0.0.0    Storage
Alias           Initialize-Volume                                  2.0.0.0    Storage
Alias           Write-FileSystemCache                              2.0.0.0    Storage
Function        Add-InitiatorIdToMaskingSet                        2.0.0.0    Storage
Function        Add-PartitionAccessPath                            2.0.0.0    Storage
Function        Add-PhysicalDisk                                   2.0.0.0    Storage
Function        Add-StorageFaultDomain                             2.0.0.0    Storage
Function        Add-TargetPortToMaskingSet                         2.0.0.0    Storage
Function        Add-VirtualDiskToMaskingSet                        2.0.0.0    Storage
Function        Block-FileShareAccess                              2.0.0.0    Storage
Function        Clear-Disk                                         2.0.0.0    Storage
Function        Clear-FileStorageTier                              2.0.0.0    Storage
Function        Clear-StorageDiagnosticInfo                        2.0.0.0    Storage
Function        Connect-VirtualDisk                                2.0.0.0    Storage
Function        Debug-FileShare                                    2.0.0.0    Storage
Function        Debug-StorageSubSystem                             2.0.0.0    Storage
Function        Debug-Volume                                       2.0.0.0    Storage
Function        Disable-PhysicalDiskIdentification                 2.0.0.0    Storage
Function        Disable-StorageEnclosureIdentification             2.0.0.0    Storage
Function        Disable-StorageEnclosurePower                      2.0.0.0    Storage
Function        Disable-StorageHighAvailability                    2.0.0.0    Storage
Function        Disable-StorageMaintenanceMode                     2.0.0.0    Storage
Function        Disconnect-VirtualDisk                             2.0.0.0    Storage
Function        Dismount-DiskImage                                 2.0.0.0    Storage
Function        Enable-PhysicalDiskIdentification                  2.0.0.0    Storage
Function        Enable-StorageEnclosureIdentification              2.0.0.0    Storage
Function        Enable-StorageEnclosurePower                       2.0.0.0    Storage
Function        Enable-StorageHighAvailability                     2.0.0.0    Storage
Function        Enable-StorageMaintenanceMode                      2.0.0.0    Storage
```

Custom Help Function

Function show-text{
Write-host "this is custom function"
}

Setting parameter as red

Function show-text{
Param($color ="red")
Write-host "this is custom function" -foregroundcolor $color
}

To check **: show-text**

```
PS C:\Users\lenovo> Function show-text{
>> Param($color ="red")
>> Write-host "this is  custom function" -foregroundcolor $color
>> }
>>
PS C:\Users\lenovo> show-text
this is  custom function
PS C:\Users\lenovo>
```

Function show-text{
Param($color ="red")
Write-host "this is custom function" -foregroundcolor $color
}

To check - **show-text -color "yellow"**

```
PS C:\Users\lenovo> Function show-text{
>> Param($color ="red")
>> Write-host "this is  custom function" -foregroundcolor $color
>> }
>>
PS C:\Users\lenovo> show-text -color "yellow"
this is  custom function
PS C:\Users\lenovo>
```

Get-help command

```
PS C:\Users\lenovo> get-help show-text

NAME
    show-text

SYNTAX
    show-text [[-color] <Object>]


ALIASES
    None


REMARKS
    None
```

Enhances the Get-Help command

Inside opening tag and closing tag <# #> we can add description, synopsis, input/output parameter, notes, link, notes.

Function show-text{
<#
.Synopsis
This is custom function to print text on console.
.Description
This is custom function to print text on console.
.PARAMETER color
This accepts a color parameter with string value
.EXAMPLE
Show-text
.EXAMPLE
Show-text -color "yellow"
#>
Param($color = "red")
Write-host "this is a custom function" -foregroundcolor $color
}

To check - **get-help show-text -full**

```
PS C:\Users\lenovo> get-help show-text -full

NAME
    show-text

SYNOPSIS
    This is custom function to print text on console.


SYNTAX
    show-text [[-color] <Object>] [<CommonParameters>]


DESCRIPTION
    This is custom function to print text on console.


PARAMETERS
    -color <Object>

        Required?                    false
        Position?                    1
        Default value                red
        Accept pipeline input?       false
        Accept wildcard characters?  false

    <CommonParameters>
        This cmdlet supports the common parameters: Verbose, Debug,
        ErrorAction, ErrorVariable, WarningAction, WarningVariable,
        OutBuffer, PipelineVariable, and OutVariable. For more information, see
        about_CommonParameters (https:/go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

OUTPUTS

    ------------------------- EXAMPLE 1 -------------------------

    PS C:\>Show-text.EXAMPLE

    Show-text -color "yellow"
```

Here we create synopsis, name, descriptions, parameter name etc
If we want to access examples we use this command
Get-help show-text -Examples

```
PS C:\Users\lenovo> get-help show-text -Examples

NAME
    show-text

SYNOPSIS
    This is custom function to print text on console.


    -------------------------- EXAMPLE 1 --------------------------

    PS C:\>Show-text





    -------------------------- EXAMPLE 2 --------------------------

    PS C:\>Show-text -color "yellow"
```

Get-help show-text -full
Once after doing this we get access to all elements created in custome function show-text

```
PS C:\Users\lenovo> get-help show-text -full

NAME
    show-text

SYNOPSIS
    This is custom function to print text on console.


SYNTAX
    show-text [[-color] <Object>] [<CommonParameters>]


DESCRIPTION
    This is custom function to print text on console.


PARAMETERS
    -color <Object>
        This accepts  a color parameter with string value

        Required?                    false
        Position?                    1
        Default value                red
        Accept pipeline input?       false
        Accept wildcard characters?  false

    <CommonParameters>
        This cmdlet supports the common parameters: Verbose, Debug,
        ErrorAction, ErrorVariable, WarningAction, WarningVariable,
        OutBuffer, PipelineVariable, and OutVariable. For more information, see
        about_CommonParameters (https:/go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

OUTPUTS

    ------------------------- EXAMPLE 1 -------------------------

    PS C:\>Show-text





    ------------------------- EXAMPLE 2 -------------------------

    PS C:\>Show-text -color "yellow"
```

This is used to create custom function where help information Is stored, where it I used by many people who access ur scripts or it is even helpful if u share ur function with someone by doing so people can understand what the script contain